

# Error Overview

© 2015 Sony Computer Entertainment Inc.  
All Rights Reserved.  
SCE Confidential

Table of Contents

1 Overview ..... 3

    Purpose ..... 3

    Error Code System ..... 3

    Handling of Errors ..... 3

    Short Error Code ..... 3

2 PSP2 Error Code Viewer ..... 4

    Overview ..... 4

    Usage Method ..... 4

3 Error Code List..... 5

    Overview ..... 5

    List ..... 5

000004892117

# 1 Overview

## Purpose

This document explains the handling of error codes in PlayStation®Vita. A system in which hexadecimal error codes are paired with short error codes is adopted in PlayStation®Vita. The short error codes are used to notify end users about the error contents.

## Error Code System

Error codes are organized as negative values expressed in the hexadecimal notation, each paired with a short error code. The error codes returned by the libraries or the system software are hexadecimal error codes. On the other hand, the error codes to be shown to the end users are short error codes based on the error code table controlled by the system software. The short error codes are defined with character strings.

The short error codes are provided to make the notification of error contents to end users easier to understand. For application development, use hexadecimal error codes.

Macro	Hexadecimal Error Code	Short Error Code
SCE_NET_ERROR_ECONNREFUSED	8041013d	NW-2465-7

## Handling of Errors

In principle, applications are required to recover from errors that occur. However, in the case of errors that are not recoverable or errors that are difficult to recover, applications are required to notify the end users of the situation with an error code according to the contents prescribed by the TRC (Technical Requirements Checklist), and terminate.

In PlayStation®Vita, error notification to the end users is performed through Message Dialog. By handing the hexadecimal error code of the error that occurred to Message Dialog API, an appropriate phrase paired to the hexadecimal error code is selected and a short error code is displayed. For details on Message Dialog, refer to the "Message Dialog Overview" document.

## Short Error Code

The short error code system is determined for each SDK. Once a code system has been determined, it continues to be used for successive SDK versions. Therefore, past short error codes remain unchanged even when error codes are added or changed.

### Format

The format of short error codes is as follows. Each short error code is made up of up to 10 characters, not including the termination character.

Short Error Code	Facility Group	Short Error Number
NW-2465-7	NW	2465-7

The facility group consists of 2 characters, such as C0 or C1. The short error number, which consists of up to 5 digits + 1 digit, is a unique number for the entire system. As an exception, error codes that are not allocated short error number use the following format.

Short Error Code	Facility Group	Hexadecimal Error Code
E-80000000	E	80000000

## 2 PSP2 Error Code Viewer


A tool "PSP2 Error Code Viewer" is provided for an efficient search of short error codes displayed through Message Dialog, etc. or hexadecimal error codes returned by the libraries.

### Overview

PSP2 Error Code Viewer is released as the following file.

- %SCE\_PSP2\_SDK\_DIR%\host\_tools\bin\psp2\_error\_code\_viewer.exe

Upon executing the above program PSP2 Error Code Viewer will start up.



### Usage Method

By inputting arbitrary character strings in the text box "Search", short error codes, hexadecimal error codes and macro names corresponding to the input character strings will be listed below. Incremental search is automatically performed according to the character strings input in the "Search" box. If two words are input ("common configured", for example), the words corresponding to the two words (in this example, SCE\_COMMON\_DIALOG\_ERROR\_NOT\_CONFIGURED) will be displayed.

In addition, by checking the "Use Regular Expression Search" checkbox, regular expressions can also be used. The grammar of regular expression complies with the following.

- <https://msdn.microsoft.com/en-us/library/az24scfc.aspx>  
(The above reference destination has been confirmed as of March 4, 2015. Note that pages may have been subsequently moved or its contents modified.)

If inputting "kernel.\*(flags | argument)", for example, the error codes that correspond to a kernel error and that are followed by a character string containing 'flags' or 'argument' will be displayed.

## 3 Error Code List

### Overview

Hexadecimal error code and short error code correspond one to one. For details about the error codes, refer to the each relevant document.

### List

The error code list is as follows.

A list of the error codes in the form of a CSV file is available at the following location:

%SCE\_PSP2\_SDK\_DIR%\host\_tools\debugging\error\_code\error\_table.csv

Short Error Code	Hexadecimal Error Code	Macro
C2-2000-2	0x80100600	SCE_APPUTIL_ERROR_PARAMETER
C2-2001-3	0x80100601	SCE_APPUTIL_ERROR_NOT_INITIALIZED
C2-2002-4	0x80100602	SCE_APPUTIL_ERROR_NO_MEMORY
C2-2003-5	0x80100603	SCE_APPUTIL_ERROR_BUSY
C2-2004-6	0x80100604	SCE_APPUTIL_ERROR_NOT_MOUNTED
C2-2005-7	0x80100640	SCE_APPUTIL_ERROR_SAVEDATA_SLOT_EXISTS
C2-2006-8	0x80100641	SCE_APPUTIL_ERROR_SAVEDATA_SLOT_NOT_FOUND
C2-2007-9	0x80100642	SCE_APPUTIL_ERROR_SAVEDATA_NO_SPACE_QUOTA
C1-2008-0	0x80020401	SCE_COMMON_DIALOG_ERROR_BUSY
C1-2009-1	0x80020402	SCE_COMMON_DIALOG_ERROR_NULL
C1-2010-3	0x80020403	SCE_COMMON_DIALOG_ERROR_INVALID_ARGUMENT
C1-2011-4	0x80020410	SCE_COMMON_DIALOG_ERROR_NOT_FINISHED
C1-2012-5	0x80020411	SCE_COMMON_DIALOG_ERROR_NOT_IN_USE
C1-2013-6	0x80020420	SCE_COMMON_DIALOG_ERROR_INVALID_COLOR_FORMAT
C1-2014-7	0x8002047f	SCE_COMMON_DIALOG_ERROR_UNEXPECTED_FATAL
C2-2015-8	0x80100a01	SCE_MSG_DIALOG_ERROR_PARAM
C2-2016-9	0x80100c01	SCE_NETCHECK_DIALOG_ERROR_PARAM
C2-2017-0	0x80100c02	SCE_NETCHECK_DIALOG_ERROR_INVALID_MODE
C2-2018-1	0x80100b01	SCE_SAVEDATA_DIALOG_ERROR_PARAM
NW-2019-2	0x80412101	SCE_NET_CTL_ERROR_NOT_INITIALIZED
NW-2020-4	0x80412102	SCE_NET_CTL_ERROR_NOT_TERMINATED
NW-2021-5	0x80412103	SCE_NET_CTL_ERROR_CALLBACK_MAX
NW-2022-6	0x80412104	SCE_NET_CTL_ERROR_ID_NOT_FOUND
NW-2023-7	0x80412105	SCE_NET_CTL_ERROR_INVALID_ID
NW-2024-8	0x80412106	SCE_NET_CTL_ERROR_INVALID_CODE
NW-2025-9	0x80412107	SCE_NET_CTL_ERROR_INVALID_ADDR
NW-2026-0	0x80412108	SCE_NET_CTL_ERROR_NOT_CONNECTED
NW-2027-1	0x80412109	SCE_NET_CTL_ERROR_NOT_AVAIL
NW-2028-2	0x8041210a	SCE_NET_CTL_ERROR_AUTO_CONNECT_DISABLED
NW-2029-3	0x8041210b	SCE_NET_CTL_ERROR_AUTO_CONNECT_FAILED
NW-2030-5	0x8041210c	SCE_NET_CTL_ERROR_NO_SUITABLE_SETTING_FOR_AUTO_CONNECT
NW-2031-6	0x8041210d	SCE_NET_CTL_ERROR_DISCONNECTED_FOR_ADHOC_USE
NW-2032-7	0x8041210e	SCE_NET_CTL_ERROR_DISCONNECT_REQ
NW-2033-8	0x8041210f	SCE_NET_CTL_ERROR_INVALID_TYPE
NW-2034-9	0x80412110	SCE_NET_CTL_ERROR_AUTO_DISCONNECT
NP-2037-2	0x80550001	SCE_NP_ERROR_ALREADY_INITIALIZED
NP-2038-3	0x80550002	SCE_NP_ERROR_NOT_INITIALIZED
NP-2039-4	0x80550003	SCE_NP_ERROR_INVALID_ARGUMENT
NP-2040-6	0x80550004	SCE_NP_ERROR_UNKNOWN_PLATFORM_TYPE
NP-2044-0	0x80550301	SCE_NP_AUTH_ERROR_ALREADY_INITIALIZED

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-2045-1	0x80550302	SCE NP AUTH ERROR NOT INITIALIZED
NP-2046-2	0x80550303	SCE NP AUTH ERROR EINVAL
NP-2047-3	0x80550304	SCE NP AUTH ERROR ENOMEM
NP-2048-4	0x80550305	SCE NP AUTH ERROR ESRCH
NP-2049-5	0x80550306	SCE NP AUTH ERROR EBUSY
NP-2050-7	0x80550307	SCE NP AUTH ERROR ABORTED
NP-2051-8	0x80550308	SCE NP AUTH ERROR INVALID SERVICE ID
NP-2052-9	0x80550309	SCE NP AUTH ERROR INVALID CREDENTIAL
NP-2053-0	0x8055030a	SCE NP AUTH ERROR INVALID ENTITLEMENT ID
NP-2054-1	0x8055030b	SCE NP AUTH ERROR INVALID DATA LENGTH
NP-2055-2	0x8055030c	SCE NP AUTH ERROR UNSUPPORTED TICKET VERSION
NP-2056-3	0x8055030d	SCE NP AUTH ERROR STACKSIZE TOO SHORT
NP-2057-4	0x8055030e	SCE NP AUTH ERROR TICKET STATUS CODE INVALID
NP-2058-5	0x8055030f	SCE NP AUTH ERROR TICKET PARAM NOT FOUND
NP-2059-6	0x80550310	SCE NP AUTH ERROR SIGNED OUT
NP-2061-9	0x80550400	SCE NP AUTH ERROR SERVICE END
NP-2062-0	0x80550401	SCE NP AUTH ERROR SERVICE DOWN
NP-2063-1	0x80550402	SCE NP AUTH ERROR SERVICE BUSY
NP-2064-2	0x80550410	SCE NP AUTH ERROR S INVALID DATA LENGTH
NP-2065-3	0x80550411	SCE NP AUTH ERROR S INVALID USER AGENT
NP-2066-4	0x80550412	SCE NP AUTH ERROR S INVALID VERSION
NP-2067-5	0x80550420	SCE NP AUTH ERROR S INVALID SERVICE ID
NP-2068-6	0x80550421	SCE NP AUTH ERROR S INVALID CREDENTIAL
NP-2069-7	0x80550422	SCE NP AUTH ERROR S INVALID ENTITLEMENT ID
NP-2070-9	0x80550423	SCE NP AUTH ERROR S INVALID CONSUMED COUNT
NP-2071-0	0x80550424	SCE NP AUTH ERROR INVALID CONSOLE ID
NP-2072-1	0x80550427	SCE NP AUTH ERROR CONSOLE ID SUSPENDED
NP-2073-2	0x80550430	SCE NP AUTH ERROR ACCOUNT CLOSED
NP-2074-3	0x80550431	SCE NP AUTH ERROR ACCOUNT SUSPENDED
NP-2075-4	0x80550432	SCE NP AUTH ERROR ACCOUNT RENEW EULA
NP-2076-5	0x80550440	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT1
NP-2077-6	0x80550441	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT2
NP-2078-7	0x80550442	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT3
NP-2079-8	0x80550443	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT4
NP-2080-0	0x80550444	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT5
NP-2081-1	0x80550445	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT6
NP-2082-2	0x80550446	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT7
NP-2083-3	0x80550447	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT8
NP-2084-4	0x80550448	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT9
NP-2085-5	0x80550449	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT10
NP-2086-6	0x8055044a	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT11
NP-2087-7	0x8055044b	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT12
NP-2088-8	0x8055044c	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT13
NP-2089-9	0x8055044d	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT14
NP-2090-1	0x8055044e	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT15
NP-2091-2	0x8055044f	SCE NP AUTH ERROR ACCOUNT RENEW ACCOUNT16   SCE NP AUTH ERROR SUB ACCOUNT RENEW EULA
NP-2092-3	0x80550480	SCE NP AUTH ERROR UNKNOWN
NP-2093-4	0x80550501	SCE NP MANAGER ERROR ALREADY INITIALIZED
NP-2094-5	0x80550502	SCE NP MANAGER ERROR NOT INITIALIZED
NP-2095-6	0x80550503	SCE NP MANAGER ERROR INVALID ARGUMENT
NP-2096-7	0x80550504	SCE NP MANAGER ERROR OUT OF MEMORY
NP-2097-8	0x80550505	SCE NP MANAGER ERROR INVALID TICKET SIZE
NP-2098-9	0x80550506	SCE NP MANAGER ERROR INVALID STATE
NP-2099-0	0x80550507	SCE NP MANAGER ERROR ABORTED
NP-2100-3	0x80550508	SCE NP MANAGER ERROR VARIANT ACCOUNT ID
NP-2101-4	0x80550509	SCE NP MANAGER ERROR ID NOT AVAIL

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-2102-5	0x8055050a	SCE NP MANAGER ERROR SIGNOUT
NP-2103-6	0x80550601	SCE NP UTIL_ERROR_INVALID_ARGUMENT
NP-2104-7	0x80550602	SCE NP UTIL_ERROR_INSUFFICIENT
NP-2105-8	0x80550603	SCE NP UTIL_ERROR_PARSER_FAILED
NP-2106-9	0x80550604	SCE NP UTIL_ERROR_INVALID_PROTOCOL_ID
NP-2107-0	0x80550605	SCE NP UTIL_ERROR_INVALID_NP_ID
NP-2108-1	0x80550606	SCE NP UTIL_ERROR_INVALID_NP_ENV
NP-2109-2	0x80550607	SCE NP UTIL_ERROR_INVALID_NPCOMMID
NP-2110-4	0x80550608	SCE NP UTIL_ERROR_INVALID_CHARACTER
NP-2111-5	0x80550609	SCE NP UTIL_ERROR_NOT_MATCH
NP-2112-6	0x8055060a	SCE NP UTIL_ERROR_INVALID_TITLEID
NP-2113-7	0x8055060c	SCE NP UTIL_ERROR_INVALID_ESCAPE_STRING
NP-2114-8	0x8055060d	SCE NP UTIL_ERROR_UNKNOWN_TYPE
NP-2115-9	0x8055060e	SCE NP UTIL_ERROR_UNKNOWN
NP-2116-0	0x80550701	SCE NP COMMUNITY_ERROR_ALREADY_INITIALIZED
NP-2117-1	0x80550702	SCE NP COMMUNITY_ERROR_NOT_INITIALIZED
NP-2118-2	0x80550703	SCE NP COMMUNITY_ERROR_OUT_OF_MEMORY
NP-2119-3	0x80550704	SCE NP COMMUNITY_ERROR_INVALID_ARGUMENT
NP-2120-5	0x80550705	SCE NP COMMUNITY_ERROR_NO_LOGIN
NP-2121-6	0x80550706	SCE NP COMMUNITY_ERROR_TOO_MANY_OBJECTS
NP-2122-7	0x80550707	SCE NP COMMUNITY_ERROR_ABORTED
NP-2123-8	0x80550708	SCE NP COMMUNITY_ERROR_BAD_RESPONSE
NP-2124-9	0x80550709	SCE NP COMMUNITY_ERROR_BODY_TOO_LARGE
NP-2125-0	0x8055070a	SCE NP COMMUNITY_ERROR_HTTP_SERVER
NP-2126-1	0x8055070b	SCE NP COMMUNITY_ERROR_INVALID_SIGNATURE
NP-2127-2	0x8055070c	SCE NP COMMUNITY_ERROR_INSUFFICIENT_ARGUMENT
NP-2128-3	0x8055070d	SCE NP COMMUNITY_ERROR_UNKNOWN_TYPE
NP-2129-4	0x8055070e	SCE NP COMMUNITY_ERROR_INVALID_ID
NP-2130-6	0x8055070f	SCE NP COMMUNITY_ERROR_INVALID_ONLINE_ID
NP-2131-7	0x80550710	SCE NP COMMUNITY_ERROR_CONNECTION_HANDLE_ALREADY_EXISTS
NP-2132-8	0x80550711	SCE NP COMMUNITY_ERROR_INVALID_TYPE
NP-2133-9	0x80550712	SCE NP COMMUNITY_ERROR_TRANSACTION_ALREADY_END
NP-2134-0	0x80550713	SCE NP COMMUNITY_ERROR_INVALID_PARTITION
NP-2135-1	0x80550714	SCE NP COMMUNITY_ERROR_INVALID_ALIGNMENT
NP-2136-2	0x80550715	SCE NP COMMUNITY_ERROR_CLIENT_HANDLE_ALREADY_EXISTS
NP-2137-3	0x80550716	SCE NP COMMUNITY_ERROR_NO_RESOURCE
NP-2138-4	0x80550801	SCE NP COMMUNITY_SERVER_ERROR_BAD_REQUEST
NP-2139-5	0x80550802	SCE NP COMMUNITY_SERVER_ERROR_INVALID_TICKET
NP-2140-7	0x80550803	SCE NP COMMUNITY_SERVER_ERROR_INVALID_SIGNATURE
NP-2141-8	0x80550805	SCE NP COMMUNITY_SERVER_ERROR_INVALID_NPID
NP-2142-9	0x80550806	SCE NP COMMUNITY_SERVER_ERROR_FORBIDDEN
NP-2143-0	0x80550807	SCE NP COMMUNITY_SERVER_ERROR_INTERNAL_SERVER_ERROR
NP-2144-1	0x80550808	SCE NP COMMUNITY_SERVER_ERROR_VERSION_NOT_SUPPORTED
NP-2145-2	0x80550809	SCE NP COMMUNITY_SERVER_ERROR_SERVICE_UNAVAILABLE
NP-2146-3	0x8055080a	SCE NP COMMUNITY_SERVER_ERROR_PLAYER_BANNED
NP-2147-4	0x8055080b	SCE NP COMMUNITY_SERVER_ERROR_CENSORED
NP-2148-5	0x8055080c	SCE NP COMMUNITY_SERVER_ERROR_RANKING_RECORD_FORBIDDEN
NP-2149-6	0x8055080d	SCE NP COMMUNITY_SERVER_ERROR_USER_PROFILE_NOT_FOUND
NP-2150-8	0x8055080e	SCE NP COMMUNITY_SERVER_ERROR_UPLOADER_DATA_NOT_FOUND
NP-2151-9	0x8055080f	SCE NP COMMUNITY_SERVER_ERROR_QUOTA_MASTER_NOT_FOUND
NP-2152-0	0x80550810	SCE NP COMMUNITY_SERVER_ERROR_RANKING_TITLE_NOT_FOUND

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-2153-1	0x80550811	SCE NP COMMUNITY SERVER ERROR BLACKLISTED USER ID
NP-2154-2	0x80550812	SCE NP COMMUNITY SERVER ERROR GAME_RANKING_NOT_FOUN D
NP-2155-3	0x80550814	SCE NP COMMUNITY SERVER ERROR_RANKING_STORE_NOT_FOU ND
NP-2156-4	0x80550815	SCE NP COMMUNITY SERVER ERROR NOT BEST SCORE
NP-2157-5	0x80550816	SCE NP COMMUNITY SERVER ERROR_LATEST_UPDATE_NOT_FOU ND
NP-2158-6	0x80550817	SCE NP COMMUNITY SERVER ERROR_RANKING_BOARD_MASTER_ NOT FOUND
NP-2159-7	0x80550818	SCE NP COMMUNITY SERVER ERROR_RANKING_GAME_DATA_MAS TER NOT FOUND
NP-2160-9	0x80550819	SCE NP COMMUNITY SERVER ERROR_INVALID_ANTICHEAT_DAT A
NP-2161-0	0x8055081a	SCE NP COMMUNITY SERVER ERROR TOO LARGE DATA
NP-2162-1	0x8055081b	SCE NP COMMUNITY SERVER ERROR NO SUCH USER NPID
NP-2163-2	0x8055081d	SCE NP COMMUNITY SERVER ERROR_INVALID_ENVIRONMENT
NP-2164-3	0x8055081f	SCE NP COMMUNITY SERVER ERROR_INVALID_ONLINE_NAME_C HARACTER
NP-2165-4	0x80550820	SCE NP COMMUNITY SERVER ERROR_INVALID_ONLINE_NAME_L ENGTH
NP-2166-5	0x80550821	SCE NP COMMUNITY SERVER ERROR_INVALID_ABOUT_ME_CHAR ACTER
NP-2167-6	0x80550822	SCE NP COMMUNITY SERVER ERROR_INVALID_ABOUT_ME LENG TH
NP-2168-7	0x80550823	SCE NP COMMUNITY SERVER ERROR_INVALID_SCORE
NP-2169-8	0x80550824	SCE NP COMMUNITY SERVER ERROR_OVER_THE_RANKING_LIMI T
NP-2170-0	0x80550826	SCE NP COMMUNITY SERVER ERROR_FAIL_TO_CREATE_SIGNAT URE
NP-2171-1	0x80550827	SCE NP COMMUNITY SERVER ERROR_RANKING_MASTER_INFO_N OT FOUND
NP-2172-2	0x80550828	SCE NP COMMUNITY SERVER ERROR_OVER_THE_GAME_DATA LI MIT
NP-2173-3	0x8055082a	SCE NP COMMUNITY SERVER ERROR SELF DATA NOT FOUND
NP-2174-4	0x8055082b	SCE NP COMMUNITY SERVER ERROR USER NOT ASSIGNED
NP-2175-5	0x8055082c	SCE NP COMMUNITY SERVER ERROR_GAME_DATA_ALREADY_EXI STS
NP-2176-6	0x805508a0	SCE NP COMMUNITY SERVER ERROR_MATCHING_BEFORE_SERVI CE
NP-2177-7	0x805508a1	SCE NP COMMUNITY SERVER ERROR_MATCHING_END_OF_SERVI CE
NP-2178-8	0x805508a2	SCE NP COMMUNITY SERVER ERROR MATCHING MAINTENANCE
NP-2179-9	0x805508a3	SCE NP COMMUNITY SERVER ERROR_RANKING_BEFORE_SERVIC E
NP-2180-1	0x805508a4	SCE NP COMMUNITY SERVER ERROR_RANKING_END_OF_SERVIC E
NP-2181-2	0x805508a5	SCE NP COMMUNITY SERVER ERROR_RANKING MAINTENANCE
NP-2182-3	0x805508a6	SCE NP COMMUNITY SERVER ERROR NO SUCH TITLE
NP-2183-4	0x805508ff	SCE NP COMMUNITY SERVER ERROR UNSPECIFIED
NP-2217-2	0x80550f01	SCE NP COMMERCE2 ERROR NOT INITIALIZED
NP-2218-3	0x80550f02	SCE NP COMMERCE2 ERROR ALREADY INITIALIZED
NP-2219-4	0x80550f03	SCE NP COMMERCE2 ERROR_INVALID_ARGUMENT
NP-2220-6	0x80550f04	SCE NP COMMERCE2 ERROR_UNSUPPORTED_VERSION
NP-2221-7	0x80550f05	SCE NP COMMERCE2 ERROR_CTX_MAX
NP-2222-8	0x80550f06	SCE NP COMMERCE2 ERROR_INVALID_INDEX
NP-2223-9	0x80550f07	SCE NP COMMERCE2 ERROR_INVALID_SKUID

©SCEI



SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-2224-0	0x80550f08	SCE NP COMMERCE2 ERROR INVALID SKU NUM
NP-2227-3	0x80550f0b	SCE NP COMMERCE2 ERROR OUT OF MEMORY
NP-2228-4	0x80550f0c	SCE NP COMMERCE2 ERROR CTX NOT FOUND
NP-2229-5	0x80550f0d	SCE NP COMMERCE2 ERROR CTXID NOT AVAILABLE
NP-2230-7	0x80550f0e	SCE NP COMMERCE2 ERROR REQ NOT FOUND
NP-2231-8	0x80550f0f	SCE NP COMMERCE2 ERROR REQID NOT AVAILABLE
NP-2232-9	0x80550f10	SCE NP COMMERCE2 ERROR ABORTED
NP-2233-0	0x80550f11	SCE NP COMMERCE2 ERROR REQUEST BUF TOO SMALL
NP-2234-1	0x80550f12	SCE NP COMMERCE2 ERROR RESPONSE BUF TOO SMALL
NP-2235-2	0x80550f13	SCE NP COMMERCE2 ERROR COULD NOT RECV WHOLE RESPONSE DATA
NP-2236-3	0x80550f14	SCE NP COMMERCE2 ERROR INVALID RESULT DATA
NP-2237-4	0x80550f15	SCE NP COMMERCE2 ERROR UNKNOWN
NP-2238-5	0x80550f16	SCE NP COMMERCE2 ERROR SERVER MAINTENANCE
NP-2239-6	0x80550f17	SCE NP COMMERCE2 ERROR SERVER UNKNOWN
NP-2240-8	0x80550f18	SCE NP COMMERCE2 ERROR INSUFFICIENT BUF SIZE
NP-2241-9	0x80550f19	SCE NP COMMERCE2 ERROR REQ MAX
NP-2242-0	0x80550f87	SCE NP COMMERCE2 ERROR DATA NOT FOUND
NP-2243-1	0x80551001	SCE NP COMMERCE2 SERVER ERROR BAD REQUEST
NP-2244-2	0x80551002	SCE NP COMMERCE2 SERVER ERROR UNKNOWN ERROR
NP-2245-3	0x80551005	SCE NP COMMERCE2 SERVER ERROR SESSION EXPIRED
NP-2246-4	0x80551007	SCE NP COMMERCE2 SERVER ERROR ACCESS PERMISSION DENIED
NP-2247-5	0x80551011	SCE NP COMMERCE2 SERVER ERROR NO SUCH PRODUCT
NP-2248-6	0x80551013	SCE NP COMMERCE2 SERVER ERROR NOT ELIGIBILITY
NP-2249-7	0x8055101b	SCE NP COMMERCE2 SERVER ERROR ACCOUNT SUSPENDED1
NP-2250-9	0x8055101c	SCE NP COMMERCE2 SERVER ERROR ACCOUNT SUSPENDED2
NP-2251-0	0x80551020	SCE NP COMMERCE2 SERVER ERROR OVER SPENDING LIMIT
NP-2252-1	0x80551039	SCE NP COMMERCE2 SERVER ERROR EXCEEDS AGE LIMIT IN BROWSING
C0-2253-2	0x80490700	SCE SFMT19937 ERROR INVALID POINTER
C0-2254-3	0x80490701	SCE SFMT19937 ERROR INVALID STATE
C0-2255-4	0x80570001	SCE DBGFONT ERROR EXISTS
C0-2256-5	0x80570002	SCE DBGFONT ERROR INVALID FONTSIZE
C0-2257-6	0x80570003	SCE DBGFONT ERROR INVALID PIXELFORMAT
C0-2258-7	0x80570004	SCE DBGFONT ERROR INVALID ADDRESS
C0-2259-8	0x80570005	SCE DBGFONT ERROR FONT OVER
C0-2260-0	0x80570006	SCE DBGFONT ERROR INVALID POINTER
C0-2261-1	0x805b0001	SCE GXM ERROR ALREADY INITIALIZED
C0-2262-2	0x805b0002	SCE GXM ERROR OUT OF MEMORY
C0-2263-3	0x805b0003	SCE GXM ERROR INVALID VALUE
C0-2264-4	0x805b0004	SCE GXM ERROR INVALID POINTER
C0-2265-5	0x805b0005	SCE GXM ERROR INVALID ALIGNMENT
C0-2266-6	0x805b0006	SCE GXM ERROR NOT WITHIN SCENE
C0-2267-7	0x805b0007	SCE GXM ERROR WITHIN SCENE
C0-2268-8	0x805b0008	SCE GXM ERROR NULL PROGRAM
C0-2269-9	0x805b0009	SCE GXM ERROR UNSUPPORTED
C0-2270-1	0x805b000a	SCE GXM ERROR PATCHER INTERNAL
C0-2271-2	0x805b000b	SCE GXM ERROR RESERVE FAILED
C0-2272-3	0x805b000c	SCE GXM ERROR PROGRAM IN USE
C0-2273-4	0x805b000d	SCE GXM ERROR INVALID INDEX COUNT
C0-2274-5	0x805b000e	SCE GXM ERROR INVALID POLYGON MODE
C0-2275-6	0x805b000f	SCE GXM ERROR INVALID SAMPLER RESULT TYPE PRECISION
C0-2276-7	0x805b0010	SCE GXM ERROR INVALID SAMPLER RESULT TYPE COMPONENT COUNT
C0-2277-8	0x805b0011	SCE GXM ERROR UNIFORM BUFFER NOT RESERVED
C0-2279-0	0x805b0014	SCE GXM ERROR INVALID PRECOMPUTED DRAW

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-2280-2	0x805b0015	SCE_GXM_ERROR_INVALID_PRECOMPUTED_VERTEX_STATE
C0-2281-3	0x805b0016	SCE_GXM_ERROR_INVALID_PRECOMPUTED_FRAGMENT_STATE
NW-2282-4	0x80431001	SCE_HTTP_ERROR_BEFORE_INIT
NW-2283-5	0x80431020	SCE_HTTP_ERROR_ALREADY_INITED
NW-2284-6	0x80431021	SCE_HTTP_ERROR_BUSY
NW-2285-7	0x80431022	SCE_HTTP_ERROR_OUT_OF_MEMORY
NW-2286-8	0x80431025	SCE_HTTP_ERROR_NOT_FOUND
NW-2287-9	0x8043106a	SCE_HTTP_ERROR_INVALID_VERSION
NW-2288-0	0x80431100	SCE_HTTP_ERROR_INVALID_ID
NW-2289-1	0x80431104	SCE_HTTP_ERROR_OUT_OF_SIZE
NW-2290-3	0x804311fe	SCE_HTTP_ERROR_INVALID_VALUE
NW-2291-4	0x80433060	SCE_HTTP_ERROR_INVALID_URL
NW-2292-5	0x80431061	SCE_HTTP_ERROR_UNKNOWN_SCHEME
NW-2293-6	0x80431064	SCE_HTTP_ERROR_BAD_RESPONSE
NW-2294-7	0x80431065	SCE_HTTP_ERROR_BEFORE_SEND
NW-2295-8	0x80431066	SCE_HTTP_ERROR_AFTER_SEND
NW-2296-9	0x80431069	SCE_HTTP_ERROR_UNKNOWN_AUTH_TYPE
NW-2297-0	0x8043106b	SCE_HTTP_ERROR_UNKNOWN_METHOD
NW-2298-1	0x8043106f	SCE_HTTP_ERROR_READ_BY_HEAD_METHOD
NW-2299-2	0x80431070	SCE_HTTP_ERROR_NOT_IN_COM
NW-2300-5	0x80431071	SCE_HTTP_ERROR_NO_CONTENT_LENGTH
NW-2301-6	0x80431072	SCE_HTTP_ERROR_CHUNK_ENC
NW-2302-7	0x80431073	SCE_HTTP_ERROR_TOO_LARGE_RESPONSE_HEADER
NW-2303-8	0x80431080	SCE_HTTP_ERROR_ABORTED
NW-2304-9	0x80432025	SCE_HTTP_ERROR_PARSE_HTTP_NOT_FOUND
NW-2305-0	0x80432060	SCE_HTTP_ERROR_PARSE_HTTP_INVALID_RESPONSE
NW-2306-1	0x804321fe	SCE_HTTP_ERROR_PARSE_HTTP_INVALID_VALUE
C0-2307-2	0x805d0001	SCE_GXT_ERROR_INVALID_POINTER
C0-2308-3	0x805d0002	SCE_GXT_ERROR_INVALID_ALIGNMENT
C4-2309-4	0x80251000	SCE_RTC_ERROR_INVALID_VALUE
C4-2310-6	0x80251001	SCE_RTC_ERROR_INVALID_POINTER
C4-2311-7	0x80251002	SCE_RTC_ERROR_NOT_INITIALIZED
C4-2312-8	0x80251003	SCE_RTC_ERROR_ALREADY_REGISTERD
C4-2313-9	0x80251004	SCE_RTC_ERROR_NOT_FOUND
C4-2314-0	0x80251080	SCE_RTC_ERROR_BAD_PARSE
C4-2315-1	0x80251081	SCE_RTC_ERROR_INVALID_YEAR
C4-2316-2	0x80251082	SCE_RTC_ERROR_INVALID_MONTH
C4-2317-3	0x80251083	SCE_RTC_ERROR_INVALID_DAY
C4-2318-4	0x80251084	SCE_RTC_ERROR_INVALID_HOUR
C4-2319-5	0x80251085	SCE_RTC_ERROR_INVALID_MINUTE
C4-2320-7	0x80251086	SCE_RTC_ERROR_INVALID_SECOND
C4-2321-8	0x80251087	SCE_RTC_ERROR_INVALID_MICROSECOND
C4-2322-9	0x802e0001	SCE_CAMERA_ERROR_ALREADY_INIT
C4-2323-0	0x802e0002	SCE_CAMERA_ERROR_NOT_INIT
C4-2324-1	0x802e0003	SCE_CAMERA_ERROR_ALREADY_OPEN
C4-2325-2	0x802e0004	SCE_CAMERA_ERROR_NOT_OPEN
C4-2326-3	0x802e0005	SCE_CAMERA_ERROR_ALREADY_START
C4-2327-4	0x802e0006	SCE_CAMERA_ERROR_NOT_START
C4-2328-5	0x802e0007	SCE_CAMERA_ERROR_FORMAT_UNKNOWN
C4-2329-6	0x802e0008	SCE_CAMERA_ERROR_RESOLUTION_UNKNOWN
C4-2330-8	0x802e0009	SCE_CAMERA_ERROR_BAD_FRAMERATE
C4-2331-9	0x802e000a	SCE_CAMERA_ERROR_TIMEOUT
C4-2332-0	0x802e000b	SCE_CAMERA_ERROR_EXCLUSIVE
C4-2333-1	0x802e000c	SCE_CAMERA_ERROR_ATTRIBUTE_UNKNOWN
C4-2334-2	0x802e000d	SCE_CAMERA_ERROR_MAX_PROCESS
C4-2335-3	0x802e000e	SCE_CAMERA_ERROR_NOT_ACTIVE
C4-2336-4	0x802e00ff	SCE_CAMERA_ERROR_FATAL

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C4-2337-5	0x80360200	SCE_POS_MOTION_ERROR_DATA_INVALID SCE_MOTION_ERROR_DATA_INVALID
C4-2338-6	0x80360201	SCE_POS_MOTION_ERROR_READING SCE_MOTION_ERROR_READING
C4-2339-7	0x80360202	SCE_POS_MOTION_ERROR_NON_INIT_ERR SCE_MOTION_ERROR_NON_INIT_ERR
C4-2340-9	0x80360203	SCE_POS_MOTION_ERROR_STATE_INVALID SCE_MOTION_ERROR_STATE_INVALID
C4-2341-0	0x80360204	SCE_POS_MOTION_ERROR_CALIB_READ_FAIL SCE_MOTION_ERROR_CALIB_READ_FAIL
C4-2342-1	0x80360205	SCE_POS_MOTION_ERROR_OUT_OF_BOUNDS SCE_MOTION_ERROR_OUT_OF_BOUNDS
C4-2343-2	0x80360206	SCE_POS_MOTION_ERROR_NOT_SAMPLING SCE_MOTION_ERROR_NOT_SAMPLING
C4-2344-3	0x80360207	SCE_POS_MOTION_ERROR_ALREADY_SAMPLING SCE_MOTION_ERROR_ALREADY_SAMPLING
C4-2345-4	0x80360208	SCE_POS_MOTION_ERROR_MEM_IN_USE SCE_MOTION_ERROR_MEM_IN_USE
C0-2346-5	0x80490100	SCE_MT19937_ERROR_INVALID_POINTER
C0-2347-6	0x80490101	SCE_MT19937_ERROR_INVALID_STATE
C0-2348-7	0x80450001	SCE_SNDP_ERROR_NOTINIT
C0-2349-8	0x80450002	SCE_SNDP_ERROR_PHDID
C0-2350-0	0x80450003	SCE_SNDP_ERROR_SMF
C0-2351-1	0x80450004	SCE_SNDP_ERROR_SMFCTX
C0-2352-2	0x80450005	SCE_SNDP_ERROR_FORMAT
C0-2353-3	0x80450006	SCE_SNDP_ERROR_SMFFULL
C0-2354-4	0x80450007	SCE_SNDP_ERROR_SMFID
C0-2355-5	0x80450008	SCE_SNDP_ERROR_PLAYCOUNT
C0-2356-6	0x80450009	SCE_SNDP_ERROR_NOTREADY
C0-2357-7	0x8045000a	SCE_SNDP_ERROR_PARAM
C0-2358-8	0x8045000b	SCE_SNDP_ERROR_NOTPLAY
C0-2359-9	0x8045000c	SCE_SNDP_ERROR_NOTPAUSE
C0-2360-1	0x8045000d	SCE_SNDP_ERROR_DONTSTOP
C0-2361-2	0x8045000e	SCE_SNDP_ERROR_ALREADY
C0-2362-3	0x8045000f	SCE_SNDP_ERROR_SOUNDDATAFULL
C0-2363-4	0x80450010	SCE_SNDP_ERROR_CANTALLOCATEVOICE
C0-2364-5	0x80450011	SCE_SNDP_ERROR_VOICENUM
C0-2365-6	0x80450012	SCE_SNDP_ERROR_RESERVEDVOICE
C0-2366-7	0x80450013	SCE_SNDP_ERROR_PAUSEVOICE
C0-2367-8	0x80590001	SCE_FIBER_ERROR_NULL
C0-2368-9	0x80590002	SCE_FIBER_ERROR_ALIGNMENT
C0-2369-0	0x80590003	SCE_FIBER_ERROR_RANGE
C0-2370-2	0x80590004	SCE_FIBER_ERROR_INVALID
C0-2371-3	0x80590005	SCE_FIBER_ERROR_PERMISSION
C0-2372-4	0x80590006	SCE_FIBER_ERROR_STATE
C0-2373-5	0x80590007	SCE_FIBER_ERROR_BUSY
C0-2374-6	0x80590008	SCE_FIBER_ERROR_AGAIN
C0-2375-7	0x80590009	SCE_FIBER_ERROR_FATAL
C0-2376-8	0x80560100	SCE_DEFLATE_ERROR_INVALID_FORMAT
C0-2377-9	0x80560101	SCE_DEFLATE_ERROR_INVALID_SIZE
C0-2378-0	0x80560102	SCE_DEFLATE_ERROR_NOT_SUPPORTED
C0-2379-1	0x80560103	SCE_DEFLATE_ERROR_INVALID_POINTER
C0-2380-3	0x80490a00	SCE_SFMT132049_ERROR_INVALID_POINTER
C0-2381-4	0x80490a01	SCE_SFMT132049_ERROR_INVALID_STATE
C0-2382-5	0x80420001	SCE_SAS_ERROR_NSMPL
C0-2383-6	0x80420003	SCE_SAS_ERROR_MFMT
C0-2384-7	0x80420005	SCE_SAS_ERROR_ADDRESS

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-2385-8	0x80420010	SCE SAS ERROR VOICE INDEX
C0-2386-9	0x80420011	SCE SAS ERROR NOISE CLOCK
C0-2387-0	0x80420012	SCE SAS ERROR PITCH VAL
C0-2388-1	0x80420013	SCE SAS ERROR ADSR MODE
C0-2389-2	0x80420014	SCE SAS ERROR ADPCM SIZE
C0-2390-4	0x80420015	SCE SAS ERROR LOOP MODE
C0-2391-5	0x80420016	SCE SAS ERROR INVALID STATE
C0-2392-6	0x80420018	SCE SAS ERROR VOLUME VAL
C0-2393-7	0x80420019	SCE SAS ERROR ADSR VAL
C0-2394-8	0x8042001a	SCE SAS ERROR PCM SIZE
C0-2395-9	0x8042001b	SCE SAS ERROR ATRAC3 SIZE
C0-2396-0	0x80420025	SCE SAS ERROR DISTORTION VAL
C0-2397-1	0x80420020	SCE SAS ERROR FX TYPE
C0-2398-2	0x80420021	SCE SAS ERROR FX FEEDBACK
C0-2399-3	0x80420022	SCE SAS ERROR FX DELAY
C0-2400-6	0x80420023	SCE SAS ERROR FX VOLUME VAL
C0-2401-7	0x80420024	SCE SAS ERROR FX UNAVAILABLE
C0-2402-8	0x80420030	SCE SAS ERROR BUSY
C0-2403-9	0x80420100	SCE SAS ERROR NOTINIT
C0-2404-0	0x80420101	SCE SAS ERROR ALRDYINIT
NW-2405-1	0x80410101	SCE NET ERROR EPERM
NW-2406-2	0x80410102	SCE NET ERROR ENOENT
NW-2407-3	0x80410103	SCE NET ERROR ESRCH
NW-2408-4	0x80410104	SCE NET ERROR EINTR
NW-2409-5	0x80410105	SCE NET ERROR EIO
NW-2410-7	0x80410106	SCE NET ERROR ENXIO
NW-2411-8	0x80410107	SCE NET ERROR E2BIG
NW-2412-9	0x80410108	SCE NET ERROR ENOEXEC
NW-2413-0	0x80410109	SCE NET ERROR EBADF
NW-2414-1	0x8041010a	SCE NET ERROR ECHILD
NW-2415-2	0x8041010b	SCE NET ERROR EDEADLK
NW-2416-3	0x8041010c	SCE NET ERROR ENOMEM
NW-2417-4	0x8041010d	SCE NET ERROR EACCES
NW-2418-5	0x8041010e	SCE NET ERROR EFAULT
NW-2419-6	0x8041010f	SCE NET ERROR ENOTBLK
NW-2420-8	0x80410110	SCE NET ERROR EBUSY
NW-2421-9	0x80410111	SCE NET ERROR EEXIST
NW-2422-0	0x80410112	SCE NET ERROR EXDEV
NW-2423-1	0x80410113	SCE NET ERROR ENODEV
NW-2424-2	0x80410114	SCE NET ERROR ENOTDIR
NW-2425-3	0x80410115	SCE NET ERROR EISDIR
NW-2426-4	0x80410116	SCE NET ERROR EINVAL
NW-2427-5	0x80410117	SCE NET ERROR ENFILE
NW-2428-6	0x80410118	SCE NET ERROR EMFILE
NW-2429-7	0x80410119	SCE NET ERROR ENOTTY
NW-2430-9	0x8041011a	SCE NET ERROR ETXTBSY
NW-2431-0	0x8041011b	SCE NET ERROR EFBIG
NW-2432-1	0x8041011c	SCE NET ERROR ENOSPC
NW-2433-2	0x8041011d	SCE NET ERROR ESPIPE
NW-2434-3	0x8041011e	SCE NET ERROR EROFS
NW-2435-4	0x8041011f	SCE NET ERROR EMLINK
NW-2436-5	0x80410120	SCE NET ERROR EPIPE
NW-2437-6	0x80410121	SCE NET ERROR EDOM
NW-2438-7	0x80410122	SCE NET ERROR ERANGE
NW-2439-8	0x80410123	SCE NET ERROR EAGAIN SCE NET ERROR EWouldBlock
NW-2440-0	0x80410124	SCE NET ERROR EINPROGRESS
NW-2441-1	0x80410125	SCE NET ERROR EALREADY

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NW-2442-2	0x80410126	SCE_NET_ERROR_ENOTSOCK
NW-2443-3	0x80410127	SCE_NET_ERROR_EDESTADDRREQ
NW-2444-4	0x80410128	SCE_NET_ERROR EMSGSIZE
NW-2445-5	0x80410129	SCE_NET_ERROR EPROTOTYPE
NW-2446-6	0x8041012a	SCE_NET_ERROR ENOPROTOOPT
NW-2447-7	0x8041012b	SCE_NET_ERROR EPROTONOSUPPORT
NW-2448-8	0x8041012c	SCE_NET_ERROR ESOCKTNOSUPPORT
NW-2449-9	0x8041012d	SCE_NET_ERROR EOPNOTSUPP
NW-2450-1	0x8041012e	SCE_NET_ERROR EPFNOSUPPORT
NW-2451-2	0x8041012f	SCE_NET_ERROR EAFNOSUPPORT
NW-2452-3	0x80410130	SCE_NET_ERROR EADDRINUSE
NW-2453-4	0x80410131	SCE_NET_ERROR EADDRNOTAVAIL
NW-2454-5	0x80410132	SCE_NET_ERROR ENETDOWN
NW-2455-6	0x80410133	SCE_NET_ERROR ENETUNREACH
NW-2456-7	0x80410134	SCE_NET_ERROR ENETRESET
NW-2457-8	0x80410135	SCE_NET_ERROR ECONNABORTED
NW-2458-9	0x80410136	SCE_NET_ERROR ECONNRESET
NW-2459-0	0x80410137	SCE_NET_ERROR ENOBUFS
NW-2460-2	0x80410138	SCE_NET_ERROR EISCONN
NW-2461-3	0x80410139	SCE_NET_ERROR ENOTCONN
NW-2462-4	0x8041013a	SCE_NET_ERROR ESHUTDOWN
NW-2463-5	0x8041013b	SCE_NET_ERROR ETOOMANYREFS
NW-2464-6	0x8041013c	SCE_NET_ERROR ETIMEDOUT
NW-2465-7	0x8041013d	SCE_NET_ERROR ECONNREFUSED
NW-2466-8	0x8041013e	SCE_NET_ERROR ELOOP
NW-2467-9	0x8041013f	SCE_NET_ERROR ENAMETOOLONG
NW-2468-0	0x80410140	SCE_NET_ERROR EHOSTDOWN
NW-2469-1	0x80410141	SCE_NET_ERROR EHOSTUNREACH
NW-2470-3	0x80410142	SCE_NET_ERROR ENOTEMPTY
NW-2471-4	0x80410143	SCE_NET_ERROR EPROCLIM
NW-2472-5	0x80410144	SCE_NET_ERROR EUSERS
NW-2473-6	0x80410145	SCE_NET_ERROR EDQUOT
NW-2474-7	0x80410146	SCE_NET_ERROR ESTALE
NW-2475-8	0x80410147	SCE_NET_ERROR EREMOTE
NW-2476-9	0x80410148	SCE_NET_ERROR EBADRPC
NW-2477-0	0x80410149	SCE_NET_ERROR ERPCMISMATCH
NW-2478-1	0x8041014a	SCE_NET_ERROR EPROGUNAVAIL
NW-2479-2	0x8041014b	SCE_NET_ERROR EPROGMISMATCH
NW-2480-4	0x8041014c	SCE_NET_ERROR EPROCUNAVAIL
NW-2481-5	0x8041014d	SCE_NET_ERROR ENOLCK
NW-2482-6	0x8041014e	SCE_NET_ERROR ENOSYS
NW-2483-7	0x8041014f	SCE_NET_ERROR EFTYPE
NW-2484-8	0x80410150	SCE_NET_ERROR EAUTH
NW-2485-9	0x80410151	SCE_NET_ERROR ENEEDAUTH
NW-2486-0	0x80410152	SCE_NET_ERROR EIDRM
NW-2487-1	0x80410153	SCE_NET_ERROR ENOMS
NW-2488-2	0x80410154	SCE_NET_ERROR EOVERFLOW
NW-2489-3	0x80410155	SCE_NET_ERROR EILSEQ
NW-2490-5	0x80410156	SCE_NET_ERROR ENOTSUP
NW-2491-6	0x80410157	SCE_NET_ERROR ECANCELED
NW-2492-7	0x80410158	SCE_NET_ERROR EBADMSG
NW-2493-8	0x80410159	SCE_NET_ERROR ENODATA
NW-2494-9	0x8041015a	SCE_NET_ERROR ENOSR
NW-2495-0	0x8041015b	SCE_NET_ERROR ENOSTR
NW-2496-1	0x8041015c	SCE_NET_ERROR ETIME
NW-2497-2	0x804101a0	SCE_NET_ERROR EADHOC
NW-2498-3	0x804101c8	SCE_NET_ERROR ENOTINIT

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NW-2499-4	0x804101c9	SCE_NET_ERROR_ENOLIBMEM
NW-2500-7	0x804101ca	SCE_NET_ERROR_ERESERVED202
NW-2501-8	0x804101cb	SCE_NET_ERROR_ECALLBACK
NW-2502-9	0x804101cc	SCE_NET_ERROR_EINTERNAL
NW-2503-0	0x804101cd	SCE_NET_ERROR_ERETURN
NW-2504-1	0x804101dc	SCE_NET_ERROR_RESOLVER_EINTERNAL
NW-2505-2	0x804101dd	SCE_NET_ERROR_RESOLVER_EBUSY
NW-2506-3	0x804101de	SCE_NET_ERROR_RESOLVER_ENOSPACE
NW-2507-4	0x804101df	SCE_NET_ERROR_RESOLVER_EPACKET
NW-2508-5	0x804101e0	SCE_NET_ERROR_RESOLVER_ERESERVED224
NW-2509-6	0x804101e1	SCE_NET_ERROR_RESOLVER_ENODNS
NW-2510-8	0x804101e2	SCE_NET_ERROR_RESOLVER_ETIMEOUT
NW-2511-9	0x804101e3	SCE_NET_ERROR_RESOLVER_ENOSUPPORT
NW-2512-0	0x804101e4	SCE_NET_ERROR_RESOLVER_EFORMAT
NW-2513-1	0x804101e5	SCE_NET_ERROR_RESOLVER_ESERVERFAILURE
NW-2514-2	0x804101e6	SCE_NET_ERROR_RESOLVER_ENOHOST
NW-2515-3	0x804101e7	SCE_NET_ERROR_RESOLVER_ENOTIMPLEMENTED
NW-2516-4	0x804101e8	SCE_NET_ERROR_RESOLVER_ESERVERREFUSED
NW-2517-5	0x804101e9	SCE_NET_ERROR_RESOLVER_ENORECORD
NW-2518-6	0x804101ea	SCE_NET_ERROR_RESOLVER_EALIGNMENT
C0-2519-7	0x80490200	SCE_SFMT607_ERROR_INVALID_POINTER
C0-2520-9	0x80490201	SCE_SFMT607_ERROR_INVALID_STATE
C0-2532-2	0x80490300	SCE_SFMT1279_ERROR_INVALID_POINTER
C0-2533-3	0x80490301	SCE_SFMT1279_ERROR_INVALID_STATE
C0-2534-4	0x80690001	SCE_PNG_ERROR_INVALID_FORMAT
C0-2535-5	0x80690002	SCE_PNG_ERROR_INVALID_SIZE
C0-2536-6	0x80690003	SCE_PNG_ERROR_NOT_SUPPORTED
C0-2537-7	0x80480500	SCE_SHA256_ERROR_INVALID_POINTER
C0-2538-8	0x80480501	SCE_SHA256_ERROR_INVALID_STATE
C1-2539-9	0x80020001	SCE_KERNEL_ERROR_ERROR
C1-2540-1	0x80020002	SCE_KERNEL_ERROR_NOT_IMPLEMENTED
C1-2541-2	0x80020003	SCE_KERNEL_ERROR_NOSYS
C1-2542-3	0x80020004	SCE_KERNEL_ERROR_UNSUP
C1-2543-4	0x80020005	SCE_KERNEL_ERROR_INVALID_ARGUMENT
C1-2544-5	0x80020006	SCE_KERNEL_ERROR_ILLEGAL_ADDR
C1-2545-6	0x80020007	SCE_KERNEL_ERROR_ILLEGAL_ALIGNMENT
C1-2546-7	0x80020008	SCE_KERNEL_ERROR_ILLEGAL_PERMISSION
C1-2547-8	0x80020009	SCE_KERNEL_ERROR_INVALID_ARGUMENT_SIZE
C1-2548-9	0x80022000	SCE_KERNEL_ERROR_CPU_ERROR
C1-2549-0	0x80022001	SCE_KERNEL_ERROR_MMU_ILLEGAL_L1_TYPE
C1-2550-2	0x80022002	SCE_KERNEL_ERROR_MMU_L2_INDEX_OVERFLOW
C1-2551-3	0x80022003	SCE_KERNEL_ERROR_MMU_L2_SIZE_OVERFLOW
C1-2552-4	0x80022004	SCE_KERNEL_ERROR_INVALID_CPU_AFFINITY
C1-2553-5	0x80022005	SCE_KERNEL_ERROR_INVALID_MEMORY_ACCESS
C1-2554-6	0x80022006	SCE_KERNEL_ERROR_INVALID_MEMORY_ACCESS_PERMISSION
C1-2555-7	0x80022007	SCE_KERNEL_ERROR_VA2PA_FAULT
C1-2556-8	0x80022008	SCE_KERNEL_ERROR_VA2PA_MAPPED
C1-2557-9	0x80022009	SCE_KERNEL_ERROR_VALIDATION_CHECK_FAILED
C1-2558-0	0x80024000	SCE_KERNEL_ERROR_SYSMEM_ERROR
C1-2559-1	0x80024001	SCE_KERNEL_ERROR_INVALID_PROCESS_CONTEXT
C1-2560-3	0x80024002	SCE_KERNEL_ERROR_UID_NAME_TOO_LONG
C1-2561-4	0x80024003	SCE_KERNEL_ERROR_VARANGE_IS_NOT_PHYSICAL_CONTINUOUS
C1-2562-5	0x80024100	SCE_KERNEL_ERROR_PHYADDR_ERROR
C1-2563-6	0x80024101	SCE_KERNEL_ERROR_NO_PHYADDR
C1-2564-7	0x80024102	SCE_KERNEL_ERROR_PHYADDR_USED
C1-2565-8	0x80024103	SCE_KERNEL_ERROR_PHYADDR_NOT_USED
C1-2566-9	0x80024104	SCE_KERNEL_ERROR_NO_IOADDR

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-2567-0	0x80024300	SCE_KERNEL_ERROR_PHYMEM_ERROR
C1-2568-1	0x80024301	SCE_KERNEL_ERROR_ILLEGAL_PHYPAGE_STATUS
C1-2569-2	0x80024302	SCE_KERNEL_ERROR_NO_FREE_PHYSICAL_PAGE
C1-2570-4	0x80024303	SCE_KERNEL_ERROR_NO_FREE_PHYSICAL_PAGE_UNIT
C1-2571-5	0x80024304	SCE_KERNEL_ERROR_PHYMEMPART_NOT_EMPTY
C1-2572-6	0x80024400	SCE_KERNEL_ERROR_FIXEDHEAP_ERROR
C1-2573-7	0x80024401	SCE_KERNEL_ERROR_FIXEDHEAP_ILLEGAL_SIZE
C1-2574-8	0x80024402	SCE_KERNEL_ERROR_FIXEDHEAP_ILLEGAL_INDEX
C1-2575-9	0x80024403	SCE_KERNEL_ERROR_FIXEDHEAP_INDEX_OVERFLOW
C1-2576-0	0x80024404	SCE_KERNEL_ERROR_FIXEDHEAP_NO_CHUNK
C1-2577-1	0x80024500	SCE_KERNEL_ERROR_UID_ERROR
C1-2578-2	0x80024501	SCE_KERNEL_ERROR_INVALID_UID
C1-2579-3	0x80024502	SCE_KERNEL_ERROR_SYSMEM_UID_INVALID_ARGUMENT
C1-2580-5	0x80024503	SCE_KERNEL_ERROR_SYSMEM_INVALID_UID_RANGE
C1-2581-6	0x80024504	SCE_KERNEL_ERROR_SYSMEM_NO_VALID_UID
C1-2582-7	0x80024505	SCE_KERNEL_ERROR_SYSMEM_CANNOT_ALLOCATE_UIDENTRY
C1-2583-8	0x80024506	SCE_KERNEL_ERROR_NOT_PROCESS_UID
C1-2584-9	0x80024507	SCE_KERNEL_ERROR_NOT_KERNEL_UID
C1-2585-0	0x80024508	SCE_KERNEL_ERROR_INVALID_UID_CLASS
C1-2586-1	0x80024509	SCE_KERNEL_ERROR_INVALID_UID_SUBCLASS
C1-2587-2	0x8002450a	SCE_KERNEL_ERROR_UID_CANNOT_FIND_BY_NAME
C1-2588-3	0x80024600	SCE_KERNEL_ERROR_VIRPAGE_ERROR
C1-2589-4	0x80024601	SCE_KERNEL_ERROR_ILLEGAL_VIRPAGE_TYPE
C1-2590-6	0x80024700	SCE_KERNEL_ERROR_BLOCK_ERROR
C1-2591-7	0x80024701	SCE_KERNEL_ERROR_ILLEGAL_BLOCK_ID
C1-2592-8	0x80024702	SCE_KERNEL_ERROR_ILLEGAL_BLOCK_TYPE
C1-2593-9	0x80024703	SCE_KERNEL_ERROR_BLOCK_IN_USE
C1-2594-0	0x80024800	SCE_KERNEL_ERROR_PARTITION_ERROR
C1-2595-1	0x80024801	SCE_KERNEL_ERROR_ILLEGAL_PARTITION_ID
C1-2596-2	0x80024802	SCE_KERNEL_ERROR_ILLEGAL_PARTITION_INDEX
C1-2597-3	0x80024900	SCE_KERNEL_ERROR_HEAPLIB_ERROR
C1-2598-4	0x80024901	SCE_KERNEL_ERROR_ILLEGAL_HEAP_ID
C1-2599-5	0x80024902	SCE_KERNEL_ERROR_OUT_OF_RANG
C1-2600-8	0x80024903	SCE_KERNEL_ERROR_HEAPLIB_NOMEM
C1-2601-9	0x80024a00	SCE_KERNEL_ERROR_SYSMEM_ADDRESS_SPACE_ERROR
C1-2602-0	0x80024a01	SCE_KERNEL_ERROR_INVALID_ADDRESS_SPACE_ID
C1-2603-1	0x80024a02	SCE_KERNEL_ERROR_INVALID_PARTITION_INDEX
C1-2604-2	0x80024b00	SCE_KERNEL_ERROR_SYSMEM_MEMBLOCK_ERROR
C1-2605-3	0x80024b01	SCE_KERNEL_ERROR_ILLEGAL_MEMBLOCK_TYPE
C1-2606-4	0x80024b02	SCE_KERNEL_ERROR_ILLEGAL_MEMBLOCK_REMAP_TYPE
C1-2607-5	0x80024b03	SCE_KERNEL_ERROR_NOT_PHY_CONT_MEMBLOCK
C1-2608-6	0x80024c00	SCE_KERNEL_ERROR_SYSMEM_PHYMEMLOW_ERROR
C1-2609-7	0x80024c01	SCE_KERNEL_ERROR_CANNOT_ALLOC_PHYMEMLOW
C1-2610-9	0x80024d00	SCE_KERNEL_ERROR_SYSMEM_BITHEAP_ERROR
C1-2611-0	0x80024d01	SCE_KERNEL_ERROR_CANNOT_ALLOC_BITHEAP
C1-2612-1	0x80025000	SCE_KERNEL_ERROR_LOADCORE_ERROR
C1-2613-2	0x80025001	SCE_KERNEL_ERROR_ILLEGAL_ELF_HEADER
C1-2614-3	0x80025002	SCE_KERNEL_ERROR_ILLEGAL_SELF_HEADER
C1-2615-4	0x80027000	SCE_KERNEL_ERROR_EXCPMGR_ERROR
C1-2616-5	0x80027001	SCE_KERNEL_ERROR_ILLEGAL_EXCPCODE
C1-2617-6	0x80027002	SCE_KERNEL_ERROR_ILLEGAL_EXCPHANDLER
C1-2618-7	0x80027003	SCE_KERNEL_ERROR_NOTFOUND_EXCPHANDLER
C1-2619-8	0x80027004	SCE_KERNEL_ERROR_CANNOT_RELEASE_EXCPHANDLER
C1-2620-0	0x80027100	SCE_KERNEL_ERROR_INTRMGR_ERROR
C1-2621-1	0x80027101	SCE_KERNEL_ERROR_ILLEGAL_CONTEXT
C1-2622-2	0x80027102	SCE_KERNEL_ERROR_ILLEGAL_INTRCODE
C1-2623-3	0x80027103	SCE_KERNEL_ERROR_ILLEGAL_INTRPARAM

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-2624-4	0x80027104	SCE_KERNEL_ERROR_ILLEGAL_INTRPRIORITY
C1-2625-5	0x80027105	SCE_KERNEL_ERROR_ILLEGAL_TARGET_CPU
C1-2626-6	0x80027106	SCE_KERNEL_ERROR_ILLEGAL_INTRFILTER
C1-2627-7	0x80027107	SCE_KERNEL_ERROR_ILLEGAL_INTRTYPE
C1-2628-8	0x80027108	SCE_KERNEL_ERROR_ILLEGAL_HANDLER
C1-2629-9	0x80027109	SCE_KERNEL_ERROR_FOUND_HANDLER
C1-2630-1	0x8002710a	SCE_KERNEL_ERROR_NOTFOUND_HANDLER
C1-2631-2	0x8002710b	SCE_KERNEL_ERROR_NO_MEMORY
C1-2632-3	0x80027200	SCE_KERNEL_ERROR_DMACMGR_ERROR
C1-2633-4	0x80027201	SCE_KERNEL_ERROR_ALREADY_QUEUED
C1-2634-5	0x80027202	SCE_KERNEL_ERROR_NOT_QUEUED
C1-2635-6	0x80027203	SCE_KERNEL_ERROR_NOT_SETUP
C1-2636-7	0x80027204	SCE_KERNEL_ERROR_ON_TRANSFERRING
C1-2637-8	0x80027205	SCE_KERNEL_ERROR_NOT_INITIALIZED
C1-2638-9	0x80027206	SCE_KERNEL_ERROR_TRANSFERRED
C1-2639-0	0x80027207	SCE_KERNEL_ERROR_NOT_UNDER_CONTROL
C1-2640-2	0x80027300	SCE_KERNEL_ERROR_SYSTIMER_ERROR
C1-2641-3	0x80027301	SCE_KERNEL_ERROR_NO_FREE_TIMER
C1-2642-4	0x80027302	SCE_KERNEL_ERROR_TIMER_NOT_ALLOCATED
C1-2643-5	0x80027303	SCE_KERNEL_ERROR_TIMER_COUNTING
C1-2644-6	0x80027304	SCE_KERNEL_ERROR_TIMER_STOPPED
C1-2645-7	0x80028000	SCE_KERNEL_ERROR_THREADMGR_ERROR
C1-2646-8	0x80028001	SCE_KERNEL_ERROR_UNKNOWN_UID
C1-2647-9	0x80028002	SCE_KERNEL_ERROR_DIFFERENT_UID_CLASS
C1-2648-0	0x80028003	SCE_KERNEL_ERROR_ALREADY_REGISTERED
C1-2649-1	0x80028004	SCE_KERNEL_ERROR_CAN_NOT_WAIT
C1-2650-3	0x80028005	SCE_KERNEL_ERROR_WAIT_TIMEOUT
C1-2651-4	0x80028006	SCE_KERNEL_ERROR_WAIT_DELETE
C1-2652-5	0x80028007	SCE_KERNEL_ERROR_WAIT_CANCEL
C1-2677-2	0x80028020	SCE_KERNEL_ERROR_THREAD_ERROR
C1-2678-3	0x80028021	SCE_KERNEL_ERROR_UNKNOWN_THREAD_ID
C1-2679-4	0x80028022	SCE_KERNEL_ERROR_ILLEGAL_THREAD_ID
C1-2680-6	0x80028023	SCE_KERNEL_ERROR_ILLEGAL_PRIORITY
C1-2681-7	0x80028024	SCE_KERNEL_ERROR_ILLEGAL_STACK_SIZE
C1-2682-8	0x80028025	SCE_KERNEL_ERROR_ILLEGAL_CPU_AFFINITY_MASK
C1-2683-9	0x80028026	SCE_KERNEL_ERROR_ILLEGAL_THREAD_PARAM_COMBINATION
C1-2684-0	0x80028027	SCE_KERNEL_ERROR_DORMANT
C1-2685-1	0x80028028	SCE_KERNEL_ERROR_NOT_DORMANT
C1-2686-2	0x80028029	SCE_KERNEL_ERROR_RUNNING
C1-2687-3	0x8002802a	SCE_KERNEL_ERROR_DELETED
C1-2688-4	0x8002802b	SCE_KERNEL_ERROR_CAN_NOT_SUSPEND
C1-2689-5	0x8002802c	SCE_KERNEL_ERROR_THREAD_STOPPED
C1-2690-7	0x8002802d	SCE_KERNEL_ERROR_THREAD_SUSPENDED
C1-2691-8	0x8002802e	SCE_KERNEL_ERROR_NOT_SUSPENDED
C1-2692-9	0x8002802f	SCE_KERNEL_ERROR_ALREADY_DEBUG_SUSPENDED
C1-2693-0	0x80028030	SCE_KERNEL_ERROR_NOT_DEBUG_SUSPENDED
C1-2694-1	0x80028031	SCE_KERNEL_ERROR_CAN_NOT_USE_VFP
C1-2695-2	0x80028032	SCE_KERNEL_ERROR_SUSPEND_COUNT_OVF
C1-2696-3	0x80029000	SCE_KERNEL_ERROR_PROCESMGR_ERROR
C1-2697-4	0x80029001	SCE_KERNEL_ERROR_INVALID_PID
C1-2698-5	0x80029002	SCE_KERNEL_ERROR_INVALID_PROCESS_TYPE
C1-2699-6	0x80029003	SCE_KERNEL_ERROR_PLS_FULL
C1-2700-9	0x80029004	SCE_KERNEL_ERROR_INVALID_PROCESS_STATUS
C1-2701-0	0x80029005	SCE_KERNEL_ERROR_PROCESS_CALLBACK_NOTFOUND
C1-2702-1	0x80029006	SCE_KERNEL_ERROR_INVALID_BUDGET_ID
C1-2703-2	0x8002a000	SCE_KERNEL_ERROR_IOFILEMGR_ERROR
C1-2704-3	0x8002a001	SCE_KERNEL_ERROR_IO_NAME_TOO_LONG

©SCEI



SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-2705-4	0x8002a002	SCE_KERNEL_ERROR_IO_REG_DEV
C1-2706-5	0x8002a003	SCE_KERNEL_ERROR_IO_ALIAS_USED
C1-2707-6	0x8002a004	SCE_KERNEL_ERROR_IO_DEL_DEV
C1-2708-7	0x8002a005	SCE_KERNEL_ERROR_IO_WOULD_BLOCK
C1-2709-8	0x8002d000	SCE_KERNEL_ERROR_MODULEMGR_START_FAILED
C1-2710-0	0x8002d001	SCE_KERNEL_ERROR_MODULEMGR_STOP_FAIL
C1-2711-1	0x8002d002	SCE_KERNEL_ERROR_MODULEMGR_IN_USE
C1-2712-2	0x8002d003	SCE_KERNEL_ERROR_MODULEMGR_NO_LIB
C1-2713-3	0x8002d004	SCE_KERNEL_ERROR_MODULEMGR_SYSCALL_REG
C1-2714-4	0x8002d005	SCE_KERNEL_ERROR_MODULEMGR_NOMEM_LIB
C1-2715-5	0x8002d006	SCE_KERNEL_ERROR_MODULEMGR_NOMEM_STUB
C1-2716-6	0x8002d007	SCE_KERNEL_ERROR_MODULEMGR_NOMEM_SELF
C1-2717-7	0x8002d008	SCE_KERNEL_ERROR_MODULEMGR_NOMEM
C1-2718-8	0x8002d009	SCE_KERNEL_ERROR_MODULEMGR_INVALID_LIB
C1-2719-9	0x8002d00a	SCE_KERNEL_ERROR_MODULEMGR_INVALID_STUB
C1-2720-1	0x8002d00b	SCE_KERNEL_ERROR_MODULEMGR_NO_FUNC_NID
C1-2721-2	0x8002d00c	SCE_KERNEL_ERROR_MODULEMGR_NO_VAR_NID
C1-2722-3	0x8002d00d	SCE_KERNEL_ERROR_MODULEMGR_INVALID_TYPE
C1-2723-4	0x8002d00e	SCE_KERNEL_ERROR_MODULEMGR_NO_MOD_ENTRY
C1-2724-5	0x8002d00f	SCE_KERNEL_ERROR_MODULEMGR_INVALID_PROC_PARAM
C1-2725-6	0x8002d010	SCE_KERNEL_ERROR_MODULEMGR_NO_MODOBJ
C1-2726-7	0x8002d011	SCE_KERNEL_ERROR_MODULEMGR_NO_MOD
C1-2727-8	0x8002d012	SCE_KERNEL_ERROR_MODULEMGR_NO_PROCESS
C1-2728-9	0x8002d013	SCE_KERNEL_ERROR_MODULEMGR_OLD_LIB
C1-2729-0	0x8002d014	SCE_KERNEL_ERROR_MODULEMGR_STARTED
C1-2730-2	0x8002d015	SCE_KERNEL_ERROR_MODULEMGR_NOT_STARTED
C1-2731-3	0x8002d016	SCE_KERNEL_ERROR_MODULEMGR_NOT_STOPPED
C1-2732-4	0x8002d080	SCE_KERNEL_ERROR_LIBRARYDB_NOENT
C1-2733-5	0x8002d081	SCE_KERNEL_ERROR_LIBRARYDB_NO_LIB
C1-2734-6	0x8002d082	SCE_KERNEL_ERROR_LIBRARYDB_NO_MOD
C1-2735-7	0x8002f000	SCE_KERNEL_ERROR_AUTHFAIL
C1-2736-8	0x8002f001	SCE_KERNEL_ERROR_NO_AUTH
C1-2737-9	0x80010001	SCE_ERROR_ERRNO_EPERM
C1-2738-0	0x80010002	SCE_ERROR_ERRNO_ENOENT
C1-2739-1	0x80010003	SCE_ERROR_ERRNO_ESRCH
C1-2740-3	0x80010004	SCE_ERROR_ERRNO_EINTR
C1-2741-4	0x80010005	SCE_ERROR_ERRNO_EIO
C1-2742-5	0x80010006	SCE_ERROR_ERRNO_ENXIO
C1-2743-6	0x80010007	SCE_ERROR_ERRNO_E2BIG
C1-2744-7	0x80010008	SCE_ERROR_ERRNO_ENOEXEC
C1-2745-8	0x80010009	SCE_ERROR_ERRNO_EBADF
C1-2746-9	0x8001000a	SCE_ERROR_ERRNO_ECHILD
C1-2747-0	0x8001000b	SCE_ERROR_ERRNO_EAGAIN
C1-2748-1	0x8001000c	SCE_ERROR_ERRNO_ENOMEM
C1-2749-2	0x8001000d	SCE_ERROR_ERRNO_EACCES
C1-2750-4	0x8001000e	SCE_ERROR_ERRNO_EFAULT
C1-2751-5	0x8001000f	SCE_ERROR_ERRNO_ENOTBLK
C1-2752-6	0x80010010	SCE_ERROR_ERRNO_EBUSY
C1-2753-7	0x80010011	SCE_ERROR_ERRNO_EEXIST
C1-2754-8	0x80010012	SCE_ERROR_ERRNO_EXDEV
C1-2755-9	0x80010013	SCE_ERROR_ERRNO_ENODEV
C1-2756-0	0x80010014	SCE_ERROR_ERRNO_ENOTDIR
C1-2757-1	0x80010015	SCE_ERROR_ERRNO_EISDIR
C1-2758-2	0x80010016	SCE_ERROR_ERRNO_EINVAL
C1-2759-3	0x80010017	SCE_ERROR_ERRNO_ENFILE
C1-2760-5	0x80010018	SCE_ERROR_ERRNO_EMFILE
C1-2761-6	0x80010019	SCE_ERROR_ERRNO_ENOTTY

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-2762-7	0x8001001a	SCE_ERROR_ERRNO_ETXTBSY
C1-2763-8	0x8001001b	SCE_ERROR_ERRNO_EFBIG
C1-2764-9	0x8001001c	SCE_ERROR_ERRNO_ENOSPC
C1-2765-0	0x8001001d	SCE_ERROR_ERRNO_ESPIPE
C1-2766-1	0x8001001e	SCE_ERROR_ERRNO_EROFS
C1-2767-2	0x8001001f	SCE_ERROR_ERRNO_EMLINK
C1-2768-3	0x80010020	SCE_ERROR_ERRNO_EPIPE
C1-2769-4	0x80010021	SCE_ERROR_ERRNO_EDOM
C1-2770-6	0x80010022	SCE_ERROR_ERRNO_ERANGE
C1-2771-7	0x80010023	SCE_ERROR_ERRNO_ENOMSG
C1-2772-8	0x80010024	SCE_ERROR_ERRNO_EIDRM
C1-2773-9	0x80010025	SCE_ERROR_ERRNO_ECHRNG
C1-2774-0	0x80010026	SCE_ERROR_ERRNO_EL2NSYNC
C1-2775-1	0x80010027	SCE_ERROR_ERRNO_EL3HLT
C1-2776-2	0x80010028	SCE_ERROR_ERRNO_EL3RST
C1-2777-3	0x80010029	SCE_ERROR_ERRNO_ELNRNG
C1-2778-4	0x8001002a	SCE_ERROR_ERRNO_EUNATCH
C1-2779-5	0x8001002b	SCE_ERROR_ERRNO_ENOCSI
C1-2780-7	0x8001002c	SCE_ERROR_ERRNO_EL2HLT
C1-2781-8	0x8001002d	SCE_ERROR_ERRNO_EDEADLK
C1-2782-9	0x8001002e	SCE_ERROR_ERRNO_ENOLCK
C1-2783-0	0x8001002f	SCE_ERROR_ERRNO_EFORMAT
C1-2784-1	0x80010030	SCE_ERROR_ERRNO_EUNSUP
C1-2785-2	0x80010032	SCE_ERROR_ERRNO_EBADE
C1-2786-3	0x80010033	SCE_ERROR_ERRNO_EBADR
C1-2787-4	0x80010034	SCE_ERROR_ERRNO_EXFULL
C1-2788-5	0x80010035	SCE_ERROR_ERRNO_ENOANO
C1-2789-6	0x80010036	SCE_ERROR_ERRNO_EBADRQC
C1-2790-8	0x80010037	SCE_ERROR_ERRNO_EBADSLT
C1-2791-9	0x80010038	SCE_ERROR_ERRNO_EDEADLOCK
C1-2792-0	0x80010039	SCE_ERROR_ERRNO_EBFONT
C1-2793-1	0x8001003c	SCE_ERROR_ERRNO_ENOSTR
C1-2794-2	0x8001003d	SCE_ERROR_ERRNO_ENODATA
C1-2795-3	0x8001003e	SCE_ERROR_ERRNO_ETIME
C1-2796-4	0x8001003f	SCE_ERROR_ERRNO_ENOSR
C1-2797-5	0x80010040	SCE_ERROR_ERRNO_ENONET
C1-2798-6	0x80010041	SCE_ERROR_ERRNO_ENOPKG
C1-2799-7	0x80010042	SCE_ERROR_ERRNO_EREMOTE
C1-2800-0	0x80010043	SCE_ERROR_ERRNO_ENOLINK
C1-2801-1	0x80010044	SCE_ERROR_ERRNO_EADV
C1-2802-2	0x80010045	SCE_ERROR_ERRNO_ESRMNT
C1-2803-3	0x80010046	SCE_ERROR_ERRNO_ECOMM
C1-2804-4	0x80010047	SCE_ERROR_ERRNO_EPROTO
C1-2805-5	0x8001004a	SCE_ERROR_ERRNO_EMULTIHOP
C1-2806-6	0x8001004b	SCE_ERROR_ERRNO_ELBIN
C1-2807-7	0x8001004c	SCE_ERROR_ERRNO_EDOTDOT
C1-2808-8	0x8001004d	SCE_ERROR_ERRNO_EBADMSG
C1-2809-9	0x8001004f	SCE_ERROR_ERRNO_EFTYPE
C1-2810-1	0x80010050	SCE_ERROR_ERRNO_ENOTUNIQ
C1-2811-2	0x80010051	SCE_ERROR_ERRNO_EBADFD
C1-2812-3	0x80010052	SCE_ERROR_ERRNO_EREMCHG
C1-2813-4	0x80010053	SCE_ERROR_ERRNO_ELIBACC
C1-2814-5	0x80010054	SCE_ERROR_ERRNO_ELIBBAD
C1-2815-6	0x80010055	SCE_ERROR_ERRNO_ELIBSCN
C1-2816-7	0x80010056	SCE_ERROR_ERRNO_ELIBMAX
C1-2817-8	0x80010057	SCE_ERROR_ERRNO_ELIBEXEC
C1-2818-9	0x80010058	SCE_ERROR_ERRNO_ENOSYS

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-2819-0	0x80010059	SCE_ERROR_ERRNO_ENMFILE
C1-2820-2	0x8001005a	SCE_ERROR_ERRNO_ENOTEMPTY
C1-2821-3	0x8001005b	SCE_ERROR_ERRNO_ENAMETOOLONG
C1-2822-4	0x8001005c	SCE_ERROR_ERRNO_ELOOP
C1-2823-5	0x8001005f	SCE_ERROR_ERRNO_EOPNOTSUPP
C1-2824-6	0x80010060	SCE_ERROR_ERRNO_EPFNOSUPPORT
C1-2825-7	0x80010068	SCE_ERROR_ERRNO_ECONNRESET
C1-2826-8	0x80010069	SCE_ERROR_ERRNO_ENOBUFS
C1-2827-9	0x8001006a	SCE_ERROR_ERRNO_EAFNOSUPPORT
C1-2828-0	0x8001006b	SCE_ERROR_ERRNO_EPROTOTYPE
C1-2829-1	0x8001006c	SCE_ERROR_ERRNO_ENOTSOCK
C1-2830-3	0x8001006d	SCE_ERROR_ERRNO_ENOPROTOOPT
C1-2831-4	0x8001006e	SCE_ERROR_ERRNO_ESHUTDOWN
C1-2832-5	0x8001006f	SCE_ERROR_ERRNO_ECONNREFUSED
C1-2833-6	0x80010070	SCE_ERROR_ERRNO_EADDRINUSE
C1-2834-7	0x80010071	SCE_ERROR_ERRNO_ECONNABORTED
C1-2835-8	0x80010072	SCE_ERROR_ERRNO_ENETUNREACH
C1-2836-9	0x80010073	SCE_ERROR_ERRNO_ENETDOWN
C1-2837-0	0x80010074	SCE_ERROR_ERRNO_ETIMEDOUT
C1-2838-1	0x80010075	SCE_ERROR_ERRNO_EHOSTDOWN
C1-2839-2	0x80010076	SCE_ERROR_ERRNO_EHOSTUNREACH
C1-2840-4	0x80010077	SCE_ERROR_ERRNO_EINPROGRESS
C1-2841-5	0x80010078	SCE_ERROR_ERRNO_EALREADY
C1-2842-6	0x80010079	SCE_ERROR_ERRNO_EDESTADDRREQ
C1-2843-7	0x8001007a	SCE_ERROR_ERRNO_EMSGSIZE
C1-2844-8	0x8001007b	SCE_ERROR_ERRNO_EPROTONOSUPPORT
C1-2845-9	0x8001007c	SCE_ERROR_ERRNO_ESOCKTNOSUPPORT
C1-2846-0	0x8001007d	SCE_ERROR_ERRNO_EADDRNOTAVAIL
C1-2847-1	0x8001007e	SCE_ERROR_ERRNO_ENETRESET
C1-2848-2	0x8001007f	SCE_ERROR_ERRNO_EISCONN
C1-2849-3	0x80010080	SCE_ERROR_ERRNO_ENOTCONN
C1-2850-5	0x80010081	SCE_ERROR_ERRNO_ETOOMANYREFS
C1-2851-6	0x80010082	SCE_ERROR_ERRNO_EPROCLIM
C1-2852-7	0x80010083	SCE_ERROR_ERRNO_EUSERS
C1-2853-8	0x80010084	SCE_ERROR_ERRNO_EDQUOT
C1-2854-9	0x80010085	SCE_ERROR_ERRNO_ESTALE
C1-2855-0	0x80010086	SCE_ERROR_ERRNO_ENOTSUP
C1-2856-1	0x80010087	SCE_ERROR_ERRNO_ENOMEDIUM
C1-2857-2	0x80010088	SCE_ERROR_ERRNO_ENOSHARE
C1-2858-3	0x80010089	SCE_ERROR_ERRNO_ECASECLASH
C1-2859-4	0x8001008a	SCE_ERROR_ERRNO_EILSEQ
C1-2860-6	0x8001008b	SCE_ERROR_ERRNO_EOVERFLOW
C1-2861-7	0x8001008c	SCE_ERROR_ERRNO_ECANCELED
C1-2862-8	0x8001008d	SCE_ERROR_ERRNO_ENOTRECOVERABLE
C1-2863-9	0x8001008e	SCE_ERROR_ERRNO_EOWNERDEAD
C0-2864-0	0x804a0001	SCE_NGS_ERROR
C0-2865-1	0x804a0002	SCE_NGS_ERROR_INVALID_PARAM
C0-2866-2	0x804a0003	SCE_NGS_ERROR_INVALID_ALIGNMENT
C0-2867-3	0x804a0004	SCE_NGS_ERROR_NOT_IMPL
C0-2868-4	0x804a0005	SCE_NGS_ERROR_DEPENDENCY
C0-2869-5	0x804a0006	SCE_NGS_ERROR_OUT_OF_ASSETS
C0-2870-7	0x804a0007	SCE_NGS_ERROR_MODULE_NOT_AVAIL
C0-2871-8	0x804a0008	SCE_NGS_ERROR_RESOURCE_LOCKED
C0-2872-9	0x804a0009	SCE_NGS_ERROR_PARAM_OUT_OF_RANGE
C4-2873-0	0x80290001	SCE_DISPLAY_ERROR_INVALID_VALUE
C4-2874-1	0x80290002	SCE_DISPLAY_ERROR_INVALID_ADDR
C4-2875-2	0x80290003	SCE_DISPLAY_ERROR_INVALID_PIXELFORMAT

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NW-2876-3	0x80435001	SCE_SSL_ERROR_BEFORE_INIT
NW-2877-4	0x80435020	SCE_SSL_ERROR_ALREADY_INITED
NW-2878-5	0x80435022	SCE_SSL_ERROR_OUT_OF_MEMORY
C4-2879-6	0x80260001	SCE_AUDIO_OUT_ERROR_NOT_OPENED
C4-2880-8	0x80260002	SCE_AUDIO_OUT_ERROR_BUSY
C4-2881-9	0x80260003	SCE_AUDIO_OUT_ERROR_INVALID_PORT
C4-2882-0	0x80260004	SCE_AUDIO_OUT_ERROR_INVALID_POINTER
C4-2883-1	0x80260005	SCE_AUDIO_OUT_ERROR_PORT_FULL
C4-2884-2	0x80260006	SCE_AUDIO_OUT_ERROR_INVALID_SIZE
C4-2885-3	0x80260007	SCE_AUDIO_OUT_ERROR_INVALID_FORMAT
C4-2886-4	0x80260008	SCE_AUDIO_OUT_ERROR_INVALID_SAMPLE_FREQ
C4-2887-5	0x80260009	SCE_AUDIO_OUT_ERROR_INVALID_VOLUME
C4-2888-6	0x8026000a	SCE_AUDIO_OUT_ERROR_INVALID_PORT_TYPE
C4-2890-9	0x8026000c	SCE_AUDIO_OUT_ERROR_INVALID_CONF_TYPE
C4-2891-0	0x8026000d	SCE_AUDIO_OUT_ERROR_OUT_OF_MEMORY
C0-2892-1	0x80480700	SCE_SHA512_ERROR_INVALID_POINTER
C0-2893-2	0x80480701	SCE_SHA512_ERROR_INVALID_STATE
C0-2894-3	0x805a1000	SCE_SYSMODULE_ERROR_INVALID_VALUE
C0-2895-4	0x805a1001	SCE_SYSMODULE_ERROR_UNLOADED
C0-2896-5	0x805a10ff	SCE_SYSMODULE_ERROR_FATAL
C0-2897-6	0x80480300	SCE_SHA1_ERROR_INVALID_POINTER
C0-2898-7	0x80480301	SCE_SHA1_ERROR_INVALID_STATE
C0-2899-8	0x80480100	SCE_MD5_ERROR_INVALID_POINTER
C0-2900-1	0x80480101	SCE_MD5_ERROR_INVALID_STATE
C0-2901-2	0x80650003	SCE_JPEG_ERROR_IMAGE_EMPTY
C0-2902-3	0x80650004	SCE_JPEG_ERROR_BAD_MARKER_LENGTH
C0-2903-4	0x80650005	SCE_JPEG_ERROR_BAD_DHT_COUNTS
C0-2904-5	0x80650006	SCE_JPEG_ERROR_BAD_DHT_INDEX
C0-2905-6	0x80650007	SCE_JPEG_ERROR_BAD_DQT_INDEX
C0-2906-7	0x80650009	SCE_JPEG_ERROR_DECODE_ERROR
C0-2907-8	0x80650010	SCE_JPEG_ERROR_INVALID_POINTER
C0-2908-9	0x80650011	SCE_JPEG_ERROR_BAD_COMPONENT_ID
C0-2909-0	0x80650013	SCE_JPEG_ERROR_UNSUPPORTED_COLORSPACE
C0-2910-2	0x80650014	SCE_JPEG_ERROR_BAD MCU SIZE
C0-2911-3	0x80650015	SCE_JPEG_ERROR_BAD_PRECISION
C0-2912-4	0x80650016	SCE_JPEG_ERROR_UNSUPPORTED_SAMPLING
C0-2913-5	0x80650017	SCE_JPEG_ERROR_COMPONENT_COUNT
C0-2914-6	0x80650018	SCE_JPEG_ERROR_CONVERSION_NOTIMPL
C0-2915-7	0x80650019	SCE_JPEG_ERROR_EOI_EXPECTED
C0-2916-8	0x80650020	SCE_JPEG_ERROR_UNSUPPORTED_IMAGE_SIZE
C0-2917-9	0x80650021	SCE_JPEG_ERROR_NO_HUFF_TABLE
C0-2918-0	0x80650022	SCE_JPEG_ERROR_NO_QUANT_TABLE
C0-2919-1	0x80650023	SCE_JPEG_ERROR_NO_SOI
C0-2920-3	0x80650024	SCE_JPEG_ERROR_BAD_DQT_MARKER
C0-2921-4	0x80650025	SCE_JPEG_ERROR_BAD_DHT_MARKER
C0-2922-5	0x80650026	SCE_JPEG_ERROR_BAD_DRI_MARKER
C0-2923-6	0x80650027	SCE_JPEG_ERROR_BAD_SOF_MARKER
C0-2924-7	0x80650028	SCE_JPEG_ERROR_BAD_SOS_MARKER
C0-2925-8	0x80650029	SCE_JPEG_ERROR_SOF_DUPLICATE
C0-2926-9	0x80650031	SCE_JPEG_ERROR_NO_LOSSLESS_SUPPORT
C0-2927-0	0x80650032	SCE_JPEG_ERROR_NO_ARITH_SUPPORT
C0-2928-1	0x80650035	SCE_JPEG_ERROR_UNKNOWN_MARKER
C0-2929-2	0x80650036	SCE_JPEG_ERROR_BAD_RESTART_MARKER
C0-2930-4	0x80650037	SCE_JPEG_ERROR_UNEXPECTED_MARKER
C0-2931-5	0x80650038	SCE_JPEG_ERROR_INVALID_REGION
C0-2932-6	0x80650039	SCE_JPEG_ERROR_INVALID_STATE
C0-2933-7	0x80650040	SCE_JPEG_ERROR_CANNOT_CONTINUE

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-2934-8	0x80650041	SCE JPEG_ERROR_MEMORY_SIZE
C0-2935-9	0x80650042	SCE JPEG_ERROR_CANNOT_INIT
C0-2936-0	0x80650043	SCE JPEG_ERROR_CANNOT_FINISH
C0-2937-1	0x80650050	SCE JPEG_ERROR_INVALID_COLOR_FORMAT
C0-2938-2	0x80650053	SCE JPEG_ERROR_NOT_PHY_CONTINUOUS_MEMORY
C0-2939-3	0x80650060	SCE JPEG_ERROR_INVALID_DECODE_MODE
C0-2940-5	0x80650061	SCE JPEG_ERROR_BAD_PROGRESSIVE_PARAM
C0-2941-6	0x80650062	SCE JPEG_ERROR_EXCEED_MAX_SPLIT_DECODER
C0-2942-7	0x80650063	SCE JPEG_ERROR_INIT_DONE
C0-2943-8	0x80650064	SCE JPEG_ERROR_INPUT_SUSPENDED
C0-2944-9	0x80650065	SCE JPEG_ERROR_INPUT_DATA_TOO_BIG
C0-2945-0	0x80650066	SCE JPEG_ERROR_INVALID_DATA_SIZE
C4-2946-1	0x80340001	SCE CTRL_ERROR_INVALID_ARG
C4-2947-2	0x80340002	SCE CTRL_ERROR_PRIV_REQUIRED
C4-2948-3	0x803400ff	SCE CTRL_ERROR_FATAL
C0-2949-4	0x80490b00	SCE SFMT216091_ERROR_INVALID_POINTER
C0-2950-6	0x80490b01	SCE SFMT216091_ERROR_INVALID_STATE
C0-2951-7	0x80480600	SCE SHA384_ERROR_INVALID_POINTER
C0-2952-8	0x80480601	SCE SHA384_ERROR_INVALID_STATE
C0-2953-9	0x80480400	SCE SHA224_ERROR_INVALID_POINTER
C0-2954-0	0x80480401	SCE SHA224_ERROR_INVALID_STATE
C0-2955-1	0x80490900	SCE SFMT86243_ERROR_INVALID_POINTER
C0-2956-2	0x80490901	SCE SFMT86243_ERROR_INVALID_STATE
C4-2957-3	0x80260100	SCE AUDIO_IN_ERROR_FATAL
C4-2958-4	0x80260101	SCE AUDIO_IN_ERROR_INVALID_PORT
C4-2959-5	0x80260102	SCE AUDIO_IN_ERROR_INVALID_SIZE
C4-2960-7	0x80260103	SCE AUDIO_IN_ERROR_INVALID_SAMPLE_FREQ
C4-2961-8	0x80260104	SCE AUDIO_IN_ERROR_INVALID_PORT_TYPE
C4-2962-9	0x80260105	SCE AUDIO_IN_ERROR_INVALID_POINTER
C4-2963-0	0x80260106	SCE AUDIO_IN_ERROR_INVALID_PORT_PARAMETER
C4-2964-1	0x80260107	SCE AUDIO_IN_ERROR_PORT_FULL
C4-2965-2	0x80260108	SCE AUDIO_IN_ERROR_OUT_OF_MEMORY
C4-2966-3	0x80260109	SCE AUDIO_IN_ERROR_NOT_OPENED
C0-2967-4	0x80490400	SCE SFMT2281_ERROR_INVALID_POINTER
C0-2968-5	0x80490401	SCE SFMT2281_ERROR_INVALID_STATE
C4-2969-6	0x80350001	SCE TOUCH_ERROR_INVALID_ARG
C4-2970-8	0x80350002	SCE TOUCH_ERROR_PRIV_REQUIRED
C4-2971-9	0x803500ff	SCE TOUCH_ERROR_FATAL
C0-2972-0	0x80810001	SCE ULT_ERROR_NULL
C0-2973-1	0x80810002	SCE ULT_ERROR_ALIGNMENT
C0-2974-2	0x80810003	SCE ULT_ERROR_RANGE
C0-2975-3	0x80810004	SCE ULT_ERROR_INVALID
C0-2976-4	0x80810005	SCE ULT_ERROR_PERMISSION
C0-2977-5	0x80810006	SCE ULT_ERROR_STATE
C0-2978-6	0x80810007	SCE ULT_ERROR_BUSY
C0-2979-7	0x80810008	SCE ULT_ERROR_AGAIN
C0-2980-9	0x80810009	SCE ULT_ERROR_FATAL
C0-2981-0	0x80490500	SCE SFMT4253_ERROR_INVALID_POINTER
C0-2982-1	0x80490501	SCE SFMT4253_ERROR_INVALID_STATE
C0-2983-2	0x80480200	SCE SHA0_ERROR_INVALID_POINTER
C0-2984-3	0x80480201	SCE SHA0_ERROR_INVALID_STATE
C0-2985-4	0x807f0001	SCE AUDIODEC_ERROR_INVALID_TYPE
C0-2986-5	0x807f0002	SCE AUDIODEC_ERROR_INVALID_INIT_PARAM
C0-2987-6	0x807f0003	SCE AUDIODEC_ERROR_ALREADY_INITIALIZED
C0-2988-7	0x807f0004	SCE AUDIODEC_ERROR_OUT_OF_MEMORY
C0-2989-8	0x807f0005	SCE AUDIODEC_ERROR_NOT_INITIALIZED
C0-2990-0	0x807f0006	SCE AUDIODEC_ERROR_A_HANDLE_IN_USE

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-2991-1	0x807f0007	SCE_AUDIODEC_ERROR_ALL_HANDLES_IN_USE
C0-2992-2	0x807f0008	SCE_AUDIODEC_ERROR_INVALID_PTR
C0-2993-3	0x807f0009	SCE_AUDIODEC_ERROR_INVALID_HANDLE
C0-2994-4	0x807f000a	SCE_AUDIODEC_ERROR_NOT_HANDLE_IN_USE
C0-2995-5	0x807f000b	SCE_AUDIODEC_ERROR_CH_SHORTAGE
C0-2996-6	0x807f000c	SCE_AUDIODEC_ERROR_INVALID_WORD_LENGTH
C0-2997-7	0x807f000d	SCE_AUDIODEC_ERROR_INVALID_SIZE
C0-2998-8	0x807f000e	SCE_AUDIODEC_ERROR_UNSUPPORTED
C0-3002-5	0x807f2000	SCE_AUDIODEC_AT9_ERROR_INVALID_CONFIG
C0-3003-6	0x807f2800	SCE_AUDIODEC_MP3_ERROR_INVALID_CH
C0-3004-7	0x807f2801	SCE_AUDIODEC_MP3_ERROR_INVALID_MPEG_VERSION
C0-3005-8	0x807f3000	SCE_AUDIODEC_AAC_ERROR_INVALID_CH
C0-3006-9	0x80620001	SCE_AVCDEC_ERROR_INVALID_TYPE
C0-3007-0	0x80620002	SCE_AVCDEC_ERROR_INVALID_PARAM
C0-3008-1	0x80620003	SCE_AVCDEC_ERROR_OUT_OF_MEMORY
C0-3009-2	0x80620004	SCE_AVCDEC_ERROR_INVALID_STATE
C0-3010-4	0x80620005	SCE_AVCDEC_ERROR_UNSUPPORTED_IMAGE_SIZE
C0-3011-5	0x80620006	SCE_AVCDEC_ERROR_INVALID_COLOR_FORMAT
C0-3012-6	0x80620007	SCE_AVCDEC_ERROR_NOT_PHY_CONTINUOUS_MEMORY
C0-3013-7	0x80620008	SCE_AVCDEC_ERROR_ALREADY_USED
C0-3014-8	0x80620009	SCE_AVCDEC_ERROR_INVALID_POINTER
C0-3015-9	0x8062000a	SCE_AVCDEC_ERROR_ES_BUFFER_FULL
C0-3016-0	0x8062000b	SCE_AVCDEC_ERROR_INITIALIZE
C0-3017-1	0x8062000c	SCE_AVCDEC_ERROR_NOT_INITIALIZE
C0-3018-2	0x8062000d	SCE_AVCDEC_ERROR_INVALID_STREAM
C0-3019-3	0x8062000e	SCE_AVCDEC_ERROR_INVALID_ARGUMENT_SIZE
C0-3020-5	0x80490800	SCE_SFMT44497_ERROR_INVALID_POINTER
C0-3021-6	0x80490801	SCE_SFMT44497_ERROR_INVALID_STATE
C0-3022-7	0x80490600	SCE_SFMT11213_ERROR_INVALID_POINTER
C0-3023-8	0x80490601	SCE_SFMT11213_ERROR_INVALID_STATE
C4-3150-9	0x802b0001	SCE_POWER_ERROR_ALREADY_REGISTERD
C4-3151-0	0x802b0002	SCE_POWER_ERROR_CALLBACK_NOT_REGISTERD
C4-3261-2	0x80260200	SCE_AUDIO_OUT_ERROR_INVALID_FX_TYPE
C0-3548-0	0x80650200	SCE_JPEGENC_ERROR_IMAGE_SIZE
C0-3549-1	0x80650201	SCE_JPEGENC_ERROR_INSUFFICIENT_BUFFER
C0-3550-3	0x80650202	SCE_JPEGENC_ERROR_INVALID_COMPRATIO
C0-3551-4	0x80650203	SCE_JPEGENC_ERROR_INVALID_PIXELFORMAT
C0-3552-5	0x80650204	SCE_JPEGENC_ERROR_INVALID_HEADER_MODE
C0-3553-6	0x80650205	SCE_JPEGENC_ERROR_INVALID_POINTER
C0-3554-7	0x80650206	SCE_JPEGENC_ERROR_NOT_PHY_CONTINUOUS_MEMORY
C0-4722-5	0x80830001	SCE_BASE64_ERROR_INVALID_FORMAT
C0-4723-6	0x80830002	SCE_BASE64_ERROR_INVALID_VALUE
C1-5563-9	0x80024511	SCE_KERNEL_ERROR_UID_REFER_NOT_ZERO
C0-5587-5	0x80570007	SCE_DBGFONT_ERROR_INVALID_VALUE
C0-5588-6	0x80460001	SCE_FONT_ERROR_NOMEMORY SCE_PVF_ERROR_NOMEMORY
C0-5589-7	0x80460002	SCE_FONT_ERROR_LIBID SCE_PVF_ERROR_LIBID
C0-5590-9	0x80460003	SCE_FONT_ERROR_ARG SCE_PVF_ERROR_ARG
C0-5591-0	0x80460004	SCE_FONT_ERROR_NOFILE SCE_PVF_ERROR_NOFILE
C0-5592-1	0x80460005	SCE_FONT_ERROR_FILEOPEN SCE_PVF_ERROR_FILEOPEN
C0-5593-2	0x80460006	SCE_FONT_ERROR_FILECLOSE SCE_PVF_ERROR_FILECLOSE
C0-5594-3	0x80460007	SCE_FONT_ERROR_FILEREAD SCE_PVF_ERROR_FILEREAD
C0-5595-4	0x80460008	SCE_FONT_ERROR_FILESEEK SCE_PVF_ERROR_FILESEEK
C0-5596-5	0x80460009	SCE_FONT_ERROR_TOOMANYOPENED SCE_PVF_ERROR_TOOMANYOPENED
C0-5597-6	0x8046000a	SCE_FONT_ERROR_ILLEGALVERSION SCE_PVF_ERROR_ILLEGALVERSION

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-5598-7	0x8046000b	SCE_FONT_ERROR_DATAINCONSISTENT SCE_PVF_ERROR_DATAINCONSISTENT
C0-5599-8	0x8046000c	SCE_FONT_ERROR_EXPIRED SCE_PVF_ERROR_EXPIRED
C0-5600-1	0x8046000d	SCE_FONT_ERROR_REGISTRY SCE_PVF_ERROR_NOGLYPH
C0-5601-2	0x8046000e	SCE_FONT_ERROR_NOSUPPORT SCE_PVF_ERROR_NOSUPPORT
C0-5602-3	0x8046ffff	SCE_FONT_ERROR_UNKNOWN SCE_PVF_ERROR_UNKNOWN
NW-5603-4	0x80431068	SCE_HTTP_ERROR_TIMEOUT
C4-5604-5	0x802e000f	SCE_CAMERA_ERROR_ALREADY_READ
C4-5605-6	0x802e0010	SCE_CAMERA_ERROR_NOT_MOUNTED
C4-5606-7	0x80360209	SCE_POS_MOTION_ERROR_NULL_PARAMETER SCE_MOTION_ERROR_NULL_PARAMETER
C0-5607-8	0x80620801	SCE_VIDEDEC_ERROR_INVALID_TYPE
C0-5608-9	0x80620802	SCE_VIDEDEC_ERROR_INVALID_PARAM
C0-5609-0	0x80620803	SCE_VIDEDEC_ERROR_OUT_OF_MEMORY
C0-5610-2	0x80620804	SCE_VIDEDEC_ERROR_INVALID_STATE
C0-5611-3	0x80620805	SCE_VIDEDEC_ERROR_UNSUPPORTED_IMAGE_SIZE
C0-5612-4	0x80620806	SCE_VIDEDEC_ERROR_INVALID_COLOR_FORMAT
C0-5613-5	0x80620807	SCE_VIDEDEC_ERROR_NOT_PHY_CONTINUOUS_MEMORY
C0-5614-6	0x80620808	SCE_VIDEDEC_ERROR_ALREADY_USED
C0-5615-7	0x80620809	SCE_VIDEDEC_ERROR_INVALID_POINTER
C0-5616-8	0x8062080a	SCE_VIDEDEC_ERROR_ES_BUFFER_FULL
C0-5617-9	0x8062080b	SCE_VIDEDEC_ERROR_INITIALIZE
C0-5618-0	0x8062080c	SCE_VIDEDEC_ERROR_NOT_INITIALIZE
C0-5619-1	0x8062080d	SCE_VIDEDEC_ERROR_INVALID_STREAM
C0-5620-3	0x8062080e	SCE_VIDEDEC_ERROR_INVALID_ARGUMENT_SIZE
C1-5621-4	0x80021000	SCE_KERNEL_ERROR_DEBUG_ERROR
C1-5622-5	0x80021001	SCE_KERNEL_ERROR_ILLEGAL_DIPSW_NUMBER
C1-5623-6	0x80024803	SCE_KERNEL_ERROR_NO_L2PAGETABLE
C1-5624-7	0x80024b04	SCE_KERNEL_ERROR_ILLEGAL_MEMBLOCK_CODE
C1-5625-8	0x80024c02	SCE_KERNEL_ERROR_UNKNOWN_PHYMEMLOW_TYPE
C1-5626-9	0x80028033	SCE_KERNEL_ERROR_SUSPEND_COUNT_UDF
C1-5628-1	0x80029007	SCE_KERNEL_ERROR_INVALID_BUDGET_SIZE
C0-5629-2	0x804a000a	SCE_NGS_ERROR_INVALID_VOICE_TYPE
C0-5630-4	0x80860001	SCE_AUDIOENC_ERROR_INVALID_TYPE
C0-5631-5	0x80860002	SCE_AUDIOENC_ERROR_INVALID_INIT_PARAM
C0-5632-6	0x80860003	SCE_AUDIOENC_ERROR_ALREADY_INITIALIZED
C0-5633-7	0x80860004	SCE_AUDIOENC_ERROR_OUT_OF_MEMORY
C0-5634-8	0x80860005	SCE_AUDIOENC_ERROR_NOT_INITIALIZED
C0-5635-9	0x80860006	SCE_AUDIOENC_ERROR_A_HANDLE_IN_USE
C0-5636-0	0x80860007	SCE_AUDIOENC_ERROR_ALL_HANDLES_IN_USE
C0-5637-1	0x80860008	SCE_AUDIOENC_ERROR_INVALID_PTR
C0-5638-2	0x80860009	SCE_AUDIOENC_ERROR_INVALID_HANDLE
C0-5639-3	0x8086000a	SCE_AUDIOENC_ERROR_NOT_HANDLE_IN_USE
C0-5640-5	0x8086000b	SCE_AUDIOENC_ERROR_CH_SHORTAGE
C0-5641-6	0x8086000c	SCE_AUDIOENC_ERROR_INVALID_WORD_LENGTH
C0-5642-7	0x8086000d	SCE_AUDIOENC_ERROR_INVALID_SIZE
C0-5643-8	0x8086000e	SCE_AUDIOENC_ERROR_INVALID_ALIGNMENT
C0-5644-9	0x80861001	SCE_AUDIOENC_CELP_ERROR_INVALID_CONFIG
C0-5645-0	0x804d0001	SCE_SULPHA_ERROR_ALREADY_INITIALIZED
C0-5646-1	0x804d0002	SCE_SULPHA_ERROR_UNINITIALIZED
C0-5647-2	0x804d0003	SCE_SULPHA_ERROR_INVALID_VALUE
C0-5648-3	0x804d0004	SCE_SULPHA_ERROR_INVALID_POINTER
C0-5649-4	0x804d0005	SCE_SULPHA_ERROR_INVALID_HANDLE
C0-5650-6	0x804d0006	SCE_SULPHA_ERROR_INVALID_ALIGNMENT
C0-5651-7	0x804d0007	SCE_SULPHA_ERROR_OUT_OF_MEMORY
C0-5652-8	0x804d0008	SCE_SULPHA_ERROR_UNSUPPORTED
C0-5653-9	0x804d0009	SCE_SULPHA_ERROR_CONNECTION

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-5654-0	0x804d000a	SCE_SULPHA_ERROR_NETWORK_OWNERSHIP
C0-5655-1	0x804d000b	SCE_SULPHA_ERROR_INVALID_AGENT_DEF
C0-5656-2	0x804d000c	SCE_SULPHA_ERROR_INVALID_AGENT_VERSION
C0-5657-3	0x804d000d	SCE_SULPHA_ERROR_INVALID_EVENT_ID
C0-5658-4	0x804d000e	SCE_SULPHA_ERROR_NOT_CONNECTED
C0-5659-5	0x804d000f	SCE_SULPHA_ERROR_EVENT_ALREADY_SENT
C0-5660-7	0x804d0010	SCE_SULPHA_ERROR_AGENT_LIMIT_REACHED
C0-5661-8	0x804d0011	SCE_SULPHA_ERROR_CAPTURE_STARTED
C0-5662-9	0x804d0012	SCE_SULPHA_ERROR_OUT_OF_BOOKMARKS
C0-5663-0	0x807f3800	SCE_AUDIODEC_CELP_ERROR_INVALID_CONFIG
C2-5839-5	0x80100700	SCE_IME_ERROR_ALREADY_OPENED
C2-5840-7	0x80100701	SCE_IME_ERROR_NOT_OPENED
C2-5841-8	0x80100702	SCE_IME_ERROR_INVALID_POINTER
C2-5842-9	0x80100703	SCE_IME_ERROR_INVALID_PARAM
C2-5843-0	0x80100704	SCE_IME_ERROR_NO_MEMORY
C2-5844-1	0x80100705	SCE_IME_ERROR_CONNECTION_FAILED
C1-5901-5	0x80020404	SCE_COMMON_DIALOG_ERROR_NOT_RUNNING
C1-5902-6	0x80020405	SCE_COMMON_DIALOG_ERROR_NOT_SUPPORTED
NP-5910-5	0x8055050b	SCE_NP_MANAGER_ERROR_NEED_CALL_NETCHECK_DIALOG SCE_NP_MANAGER_ERROR_NOT_SIGNIN
NW-6117-5	0x80412188	SCE_NET_CTL_ERROR_UNKNOWN_DEVICE
NP-6157-9	0x80551600	SCE_NP_TROPHY_ERROR_UNKNOWN
NP-6158-0	0x80551601	SCE_NP_TROPHY_ERROR_NOT_INITIALIZED
NP-6159-1	0x80551602	SCE_NP_TROPHY_ERROR_ALREADY_INITIALIZED
NP-6160-3	0x80551603	SCE_NP_TROPHY_ERROR_NO_MEMORY
NP-6161-4	0x80551604	SCE_NP_TROPHY_ERROR_INVALID_ARGUMENT
NP-6162-5	0x80551605	SCE_NP_TROPHY_ERROR_INSUFFICIENT_BUFFER
NP-6163-6	0x80551606	SCE_NP_TROPHY_ERROR_EXCEEDS_MAX
NP-6164-7	0x80551607	SCE_NP_TROPHY_ERROR_ABORT
NP-6165-8	0x80551608	SCE_NP_TROPHY_ERROR_INVALID_HANDLE
NP-6166-9	0x80551609	SCE_NP_TROPHY_ERROR_INVALID_CONTEXT
NP-6167-0	0x8055160a	SCE_NP_TROPHY_ERROR_INVALID_NPCOMMID
NP-6168-1	0x8055160b	SCE_NP_TROPHY_ERROR_INVALID_NPCOMMSIGN
NP-6169-2	0x8055160c	SCE_NP_TROPHY_ERROR_NPCOMMSIGN_VERIFICATION_FAILURE
NP-6170-4	0x8055160d	SCE_NP_TROPHY_ERROR_INVALID_GROUP_ID
NP-6171-5	0x8055160e	SCE_NP_TROPHY_ERROR_INVALID_TROPHY_ID
NP-6172-6	0x8055160f	SCE_NP_TROPHY_ERROR_TROPHY_ALREADY_UNLOCKED
NP-6173-7	0x80551610	SCE_NP_TROPHY_ERROR_PLATINUM_CANNOT_UNLOCK
NP-6174-8	0x80551611	SCE_NP_TROPHY_ERROR_ACCOUNTID_NOT_MATCH
NP-6175-9	0x80551612	SCE_NP_TROPHY_ERROR_SETUP_REQUIRED
NP-6176-0	0x80551613	SCE_NP_TROPHY_ERROR_ALREADY_SETUP
NP-6177-1	0x80551614	SCE_NP_TROPHY_ERROR_BROKEN_DATA
NP-6178-2	0x80551615	SCE_NP_TROPHY_ERROR_INSUFFICIENT_EM_SPACE
NP-6179-3	0x80551616	SCE_NP_TROPHY_ERROR_CONTEXT_ALREADY_EXISTS
NP-6180-5	0x80551617	SCE_NP_TROPHY_ERROR_TRP_FILE_VERIFICATION_FAILURE
NP-6181-6	0x80551618	SCE_NP_TROPHY_ERROR_ICON_FILE_NOT_FOUND
NP-6182-7	0x80551619	SCE_NP_TROPHY_ERROR_TRP_FILE_NOT_FOUND
NP-6183-8	0x8055161a	SCE_NP_TROPHY_ERROR_INVALID_TRP_FILE_FORMAT
NP-6184-9	0x8055161b	SCE_NP_TROPHY_ERROR_UNSUPPORTED_TRP_FILE
NP-6185-0	0x8055161c	SCE_NP_TROPHY_ERROR_INVALID_TROPHY_CONF_FORMAT
NP-6186-1	0x8055161d	SCE_NP_TROPHY_ERROR_UNSUPPORTED_TROPHY_CONF
NP-6187-2	0x8055161e	SCE_NP_TROPHY_ERROR_TROPHY_NOT_UNLOCKED
NP-6188-3	0x8055161f	SCE_NP_TROPHY_ERROR_UNLOCK_DENIED
NP-6189-4	0x80551620	SCE_NP_TROPHY_ERROR_INSUFFICIENT_MC_SPACE
NP-6190-6	0x80551621	SCE_NP_TROPHY_ERROR_DEBUG_FAILURE
C0-6326-7	0x80820001	SCE_FIOS_ERROR_CANT_ALLOCATE_OP SCE_FIOS_KERNEL_ERROR_CANT_ALLOCATE_OP

©SCEI



SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-6327-8	0x80820002	SCE_FIOS_ERROR_CANT_ALLOCATE_FH SCE_FIOS_KERNEL_ERROR_CANT_ALLOCATE_FH
C0-6328-9	0x80820003	SCE_FIOS_ERROR_CANT_ALLOCATE_DH SCE_FIOS_KERNEL_ERROR_CANT_ALLOCATE_DH
C0-6329-0	0x80820004	SCE_FIOS_ERROR_CANT_ALLOCATE_CHUNK SCE_FIOS_KERNEL_ERROR_CANT_ALLOCATE_CHUNK
C0-6330-2	0x80820005	SCE_FIOS_ERROR_BAD_PATH SCE_FIOS_KERNEL_ERROR_BAD_PATH
C0-6331-3	0x80820006	SCE_FIOS_ERROR_BAD_PTR SCE_FIOS_KERNEL_ERROR_BAD_PTR
C0-6332-4	0x80820007	SCE_FIOS_ERROR_BAD_OFFSET SCE_FIOS_KERNEL_ERROR_BAD_OFFSET
C0-6333-5	0x80820008	SCE_FIOS_ERROR_BAD_SIZE SCE_FIOS_KERNEL_ERROR_BAD_SIZE
C0-6334-6	0x80820009	SCE_FIOS_ERROR_BAD_IOVCNT SCE_FIOS_KERNEL_ERROR_BAD_IOVCNT
C0-6335-7	0x8082000a	SCE_FIOS_ERROR_BAD_OP SCE_FIOS_KERNEL_ERROR_BAD_OP
C0-6336-8	0x8082000b	SCE_FIOS_ERROR_BAD_FH SCE_FIOS_KERNEL_ERROR_BAD_FH
C0-6337-9	0x8082000c	SCE_FIOS_ERROR_BAD_DH SCE_FIOS_KERNEL_ERROR_BAD_DH
C0-6338-0	0x8082000d	SCE_FIOS_ERROR_BAD_ALIGNMENT SCE_FIOS_KERNEL_ERROR_BAD_ALIGNMENT
C0-6339-1	0x8082000e	SCE_FIOS_ERROR_NOT_A_FILE SCE_FIOS_KERNEL_ERROR_NOT_A_FILE
C0-6340-3	0x8082000f	SCE_FIOS_ERROR_NOT_A_DIRECTORY SCE_FIOS_KERNEL_ERROR_NOT_A_DIRECTORY
C0-6341-4	0x80820010	SCE_FIOS_ERROR_EOF SCE_FIOS_KERNEL_ERROR_EOF
C0-6342-5	0x80820011	SCE_FIOS_ERROR_TIMEOUT SCE_FIOS_KERNEL_ERROR_TIMEOUT
C0-6343-6	0x80820012	SCE_FIOS_ERROR_CANCELLED SCE_FIOS_KERNEL_ERROR_CANCELLED
C0-6344-7	0x80820013	SCE_FIOS_ERROR_ACCESS SCE_FIOS_KERNEL_ERROR_ACCESS
C0-6345-8	0x80820014	SCE_FIOS_ERROR_DECOMPRESSION SCE_FIOS_KERNEL_ERROR_DECOMPRESSION
C0-6346-9	0x80820015	SCE_FIOS_ERROR_READ_ONLY SCE_FIOS_KERNEL_ERROR_READ_ONLY
C0-6347-0	0x80820016	SCE_FIOS_ERROR_WRITE_ONLY SCE_FIOS_KERNEL_ERROR_WRITE_ONLY
C0-6348-1	0x80820017	SCE_FIOS_ERROR_MEDIA_GONE SCE_FIOS_KERNEL_ERROR_MEDIA_GONE
C0-6349-2	0x80820018	SCE_FIOS_ERROR_PATH_TOO_LONG SCE_FIOS_KERNEL_ERROR_PATH_TOO_LONG
C0-6350-4	0x80820019	SCE_FIOS_ERROR_TOO_MANY_OVERLAYS SCE_FIOS_KERNEL_ERROR_TOO_MANY_OVERLAYS
C0-6351-5	0x8082001a	SCE_FIOS_ERROR_BAD_OVERLAY SCE_FIOS_KERNEL_ERROR_BAD_OVERLAY
C0-6391-9	0x80481000	SCE_HMAC_ERROR_INVALID_POINTER
C4-7728-4	0x802b0100	SCE_POWER_ERROR_NO_BATTERY
C4-7729-5	0x802b0101	SCE_POWER_ERROR_DETECTING
NP-8099-6	0x80551010	SCE_NP_COMMERCE2_SERVER_ERROR_NO_SUCH_CATEGORY
NP-8107-6	0x8055101a	SCE_NP_COMMERCE2_SERVER_ERROR_INVALID_SKU
NP-8123-4	0x8055102f	SCE_NP_COMMERCE2_SERVER_ERROR_INVALID_VOUCHER
NP-8124-5	0x80551030	SCE_NP_COMMERCE2_SERVER_ERROR_VOUCHER_ALREADY_CONSUMED
NP-8205-5	0x80550c0d	SCE_NP_MATCHING2_ERROR_INVALID_WORLD_ID
NP-8206-6	0x80550c1b	SCE_NP_MATCHING2_ERROR_INSUFFICIENT_BUFFER
NP-8207-7	0x80550c1c	SCE_NP_MATCHING2_ERROR_DESTINATION_DISAPPEARED
NP-8208-8	0x80550c1d	SCE_NP_MATCHING2_ERROR_REQUEST_TIMEOUT
NP-8249-3	0x80550d25	SCE_NP_MATCHING2_SERVER_ERROR_LOBBY_ALREADY_EXIST

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-8250-5	0x80550d26	SCE NP MATCHING2 SERVER ERROR ROOM ALREADY EXIST
NP-8251-6	0x80550d1d	SCE NP MATCHING2 SERVER ERROR GROUP PASSWORD MISMATCH
C2-8311-3	0x80100e04	SCE NP FRIENDLIST_DIALOG_ERROR_LACK_OF_LIBHTTP_POOL_SIZE
C2-8312-4	0x80100e05	SCE NP FRIENDLIST_DIALOG_ERROR_LACK_OF_LIBSSL_POOL_SIZE
C0-8447-3	0x80802000	SCE APPMGR ERROR BUSY
C0-8510-4	0x8042001c	SCE SAS ERROR CONFIG
NP-8651-0	0x80551d00	SCE NP BASIC ERROR BASE
NP-8676-7	0x80550fc1	SCE NP COMMERCE2 SM ERROR BUF TOO SMALL
NP-8678-9	0x80550c01	SCE NP MATCHING2 ERROR OUT OF MEMORY
NP-8679-0	0x80550c02	SCE NP MATCHING2 ERROR ALREADY INITIALIZED
NP-8680-2	0x80550c03	SCE NP MATCHING2 ERROR NOT INITIALIZED
NP-8681-3	0x80550c04	SCE NP MATCHING2 ERROR CONTEXT MAX
NP-8682-4	0x80550c05	SCE NP MATCHING2 ERROR CONTEXT ALREADY EXISTS
NP-8683-5	0x80550c06	SCE NP MATCHING2 ERROR CONTEXT NOT FOUND
NP-8684-6	0x80550c07	SCE NP MATCHING2 ERROR CONTEXT ALREADY STARTED
NP-8685-7	0x80550c08	SCE NP MATCHING2 ERROR CONTEXT NOT STARTED
NP-8686-8	0x80550c09	SCE NP MATCHING2 ERROR SERVER NOT FOUND
NP-8687-9	0x80550c0a	SCE NP MATCHING2 ERROR INVALID ARGUMENT
NP-8688-0	0x80550c0b	SCE NP MATCHING2 ERROR INVALID CONTEXT ID
NP-8689-1	0x80550c0c	SCE NP MATCHING2 ERROR INVALID SERVER ID
NP-8690-3	0x80550c0e	SCE NP MATCHING2 ERROR INVALID LOBBY ID
NP-8691-4	0x80550c0f	SCE NP MATCHING2 ERROR INVALID ROOM ID
NP-8692-5	0x80550c10	SCE NP MATCHING2 ERROR INVALID MEMBER ID
NP-8693-6	0x80550c11	SCE NP MATCHING2 ERROR INVALID ATTRIBUTE ID
NP-8694-7	0x80550c12	SCE NP MATCHING2 ERROR INVALID CASTTYPE
NP-8695-8	0x80550c13	SCE NP MATCHING2 ERROR INVALID SORT METHOD
NP-8696-9	0x80550c14	SCE NP MATCHING2 ERROR INVALID MAX SLOT
NP-8697-0	0x80550c15	SCE NP MATCHING2 ERROR INVALID OPT SIZE
NP-8698-1	0x80550c16	SCE NP MATCHING2 ERROR INVALID MATCHING SPACE
NP-8700-5	0x80550c18	SCE NP MATCHING2 ERROR INVALID BLOCK KICK FLAG
NP-8701-6	0x80550c19	SCE NP MATCHING2 ERROR INVALID MESSAGE TARGET
NP-8702-7	0x80550c1a	SCE NP MATCHING2 ERROR RANGE FILTER MAX
NP-8703-8	0x80550c1e	SCE NP MATCHING2 ERROR INVALID ALIGNMENT
NP-8707-2	0x80550c22	SCE NP MATCHING2 ERROR CONNECTION CLOSED BY SERVER
NP-8708-3	0x80550c23	SCE NP MATCHING2 ERROR SSL VERIFY FAILED
NP-8709-4	0x80550c24	SCE NP MATCHING2 ERROR SSL HANDSHAKE
NP-8710-6	0x80550c25	SCE NP MATCHING2 ERROR SSL SEND
NP-8711-7	0x80550c26	SCE NP MATCHING2 ERROR SSL RECV
NP-8712-8	0x80550c27	SCE NP MATCHING2 ERROR JOINED SESSION MAX
NP-8713-9	0x80550c28	SCE NP MATCHING2 ERROR ALREADY JOINED
NP-8714-0	0x80550c29	SCE NP MATCHING2 ERROR INVALID SESSION TYPE
NP-8716-2	0x80550c2b	SCE NP MATCHING2 ERROR NP SIGNED OUT
NP-8717-3	0x80550c2c	SCE NP MATCHING2 ERROR BUSY
NP-8718-4	0x80550c2d	SCE NP MATCHING2 ERROR SERVER NOT AVAILABLE
NP-8719-5	0x80550c2e	SCE NP MATCHING2 ERROR NOT ALLOWED
NP-8720-7	0x80550c2f	SCE NP MATCHING2 ERROR ABORTED
NP-8721-8	0x80550c30	SCE NP MATCHING2 ERROR REQUEST NOT FOUND
NP-8722-9	0x80550c31	SCE NP MATCHING2 ERROR SESSION DESTROYED
NP-8723-0	0x80550c32	SCE NP MATCHING2 ERROR CONTEXT STOPPED
NP-8724-1	0x80550c33	SCE NP MATCHING2 ERROR INVALID REQUEST PARAMETER
NP-8725-2	0x80550c34	SCE NP MATCHING2 ERROR NOT NP SIGN IN
NP-8726-3	0x80550c35	SCE NP MATCHING2 ERROR ROOM NOT FOUND
NP-8727-4	0x80550c36	SCE NP MATCHING2 ERROR ROOM MEMBER NOT FOUND
NP-8728-5	0x80550c37	SCE NP MATCHING2 ERROR LOBBY NOT FOUND

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-8729-6	0x80550c38	SCE NP MATCHING2_ERROR_LOBBY_MEMBER_NOT_FOUND
NP-8731-9	0x80550c3a	SCE NP MATCHING2_ERROR_KEEPA_LIVE_TIMEOUT
NP-8732-0	0x80550c3b	SCE NP MATCHING2_ERROR_TIMEOUT_TOO_SHORT
NP-8733-1	0x80550c3c	SCE NP MATCHING2_ERROR_TIMEDOUT
NP-8734-2	0x80550c3d	SCE NP MATCHING2_ERROR_INVALID_SLOTGROUP
NP-8735-3	0x80550c3e	SCE NP MATCHING2_ERROR_INVALID_ATTRIBUTE_SIZE
NP-8736-4	0x80550c3f	SCE NP MATCHING2_ERROR_CANNOT_ABORT
C0-8809-5	0x805c0001	SCE CES_ERROR_INVALID_PARAMETER
C0-8810-7	0x805c0004	SCE CES_ERROR_INVALID_PROFILE
C0-8812-9	0x805c0010	SCE CES_ERROR_INVALID_SRC_BUFFER
C0-8813-0	0x805c0011	SCE CES_ERROR_SRC_BUFFER_END
C0-8814-1	0x805c0014	SCE CES_ERROR_INVALID_ENCODE
C0-8815-2	0x805c0015	SCE CES_ERROR_ILLEGAL_CODE
C0-8816-3	0x805c0020	SCE CES_ERROR_UNASSIGNED_CODE
C0-8817-4	0x805c0024	SCE CES_ERROR_OUT_OF_CODE_RANGE
C0-8818-5	0x805c0030	SCE CES_ERROR_INVALID_DST_BUFFER
C0-8819-6	0x805c0031	SCE CES_ERROR_DST_BUFFER_END
C4-8822-0	0x80290004	SCE_DISPLAY_ERROR_INVALID_PITCH
C4-8823-1	0x80290005	SCE_DISPLAY_ERROR_INVALID_RESOLUTION
C4-8824-2	0x80290006	SCE_DISPLAY_ERROR_INVALID_UPDATE_TIMING
C1-8825-3	0x8002000a	SCE_KERNEL_ERROR_INVALID_FLAGS
C1-8826-4	0x80024305	SCE_KERNEL_ERROR_NO_PHYMEMPART_LPDDR2
C1-8827-5	0x80024306	SCE_KERNEL_ERROR_NO_PHYMEMPART_CDRAM
C1-8828-6	0x80024a03	SCE_KERNEL_ERROR_ADDRESS_SPACE_CANNOT_FIND_PARTITION_BY_ADDR
C1-8829-7	0x80024b05	SCE_KERNEL_ERROR_ILLEGAL_MEMBLOCK_SIZE
C1-8830-9	0x80024b06	SCE_KERNEL_ERROR_ILLEGAL_USERMAP_SIZE
C1-8842-2	0x8002d017	SCE_KERNEL_ERROR_MODULEMGR_INVALID_PROCESS_UID
C1-8843-3	0x80080800	SCE_KERNEL_ERROR_DEC14P_UNKNOWN
C1-8844-4	0x80080801	SCE_KERNEL_ERROR_DEC14P_ALREADYUSE_PROTOCOL
C1-8845-5	0x80080802	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_SID
C1-8846-6	0x80080803	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_CBID
C1-8847-7	0x80080804	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_ADDR
C1-8848-8	0x80080805	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_SIZE
C1-8849-9	0x80080806	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_PROTOCOL
C1-8850-1	0x80080807	SCE_KERNEL_ERROR_DEC14P_NO_MEMORY
C1-8851-2	0x80080808	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_RESERVED
C1-8852-3	0x80080809	SCE_KERNEL_ERROR_DEC14P_TOOMANY_PROTOCOL
C1-8853-4	0x8008080a	SCE_KERNEL_ERROR_DEC14P_NO_CONNECT
C1-8854-5	0x8008080b	SCE_KERNEL_ERROR_DEC14P_NO_PROTO
C1-8855-6	0x8008080c	SCE_KERNEL_ERROR_DEC14P_TOOSMALL_BUFFER
NW-8856-7	0x804101a1	SCE_NET_ERROR_EDISABLEDIF SCE_PS4LINK_RP_ERROR_NET_DISABLEDIF
C0-8857-8	0x804a000b	SCE_NGS_ERROR_SYSTEM_MISMATCH
C0-8858-9	0x80690004	SCE_PNG_ERROR_INVALID_POINTER
C0-8926-5	0x8082001b	SCE_FIOS_ERROR_BAD_ORDER SCE_FIOS_KERNEL_ERROR_BAD_ORDER
C0-8927-6	0x8082001c	SCE_FIOS_ERROR_BAD_INDEX SCE_FIOS_KERNEL_ERROR_BAD_INDEX
C0-8928-7	0x8082001d	SCE_FIOS_ERROR_EVENT_NOT_HANDLED SCE_FIOS_KERNEL_ERROR_EVENT_NOT_HANDLED
C0-8929-8	0x8082001e	SCE_FIOS_ERROR_BUSY SCE_FIOS_KERNEL_ERROR_BUSY
C0-8930-0	0x8082001f	SCE_FIOS_ERROR_BAD_ARCHIVE SCE_FIOS_KERNEL_ERROR_BAD_ARCHIVE
C1-8933-3	0x80020430	SCE_COMMON_DIALOG_ERROR_IME_IN_USE
C2-8936-6	0x80101e01	SCE_NP_FRIENDLIST_DIALOG_ERROR_INVALID_PARAM

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-8937-7	0x80101e02	SCE_NP_FRIENDLIST_DIALOG_ERROR_REQUIRED_MODULES_NOT_LOADED
C2-8938-8	0x80101e03	SCE_NP_FRIENDLIST_DIALOG_ERROR_NOT_SIGNED_IN
C2-8939-9	0x80102001	SCE_IME_DIALOG_ERROR_PARAM
C2-8940-1	0x80102002	SCE_IME_DIALOG_ERROR_INTERNAL
NW-8941-2	0x80431063	SCE_HTTP_ERROR_NETWORK
NW-8942-3	0x80431075	SCE_HTTP_ERROR_SSL
NW-8943-4	0x80431081	SCE_HTTP_ERROR_UNKNOWN
NW-8944-5	0x80431082	SCE_HTTP_ERROR_EAGAIN
C2-8945-6	0x80100750	SCE_IME_ERROR_INTERNAL
C2-8946-7	0x80101200	SCE_LOCATION_ERROR_BASE
NW-8947-8	0x80412111	SCE_NET_CTL_ERROR_INVALID_SIZE
C0-8949-0	0x80890001	SCE_SYSTEM_GESTURE_ERROR_INVALID_ARGUMENT
C0-8950-2	0x80890002	SCE_SYSTEM_GESTURE_ERROR_NOT_SUPPORTED_GESTURE
C0-8951-3	0x80890003	SCE_SYSTEM_GESTURE_ERROR_NOT_INITIALIZED
C0-8952-4	0x80890004	SCE_SYSTEM_GESTURE_ERROR_INDEX_OUT_OF_ARRAY
C0-8953-5	0x80890005	SCE_SYSTEM_GESTURE_ERROR_EVENT_DATA_NOT_FOUND
C0-9059-3	0x8062000f	SCE_AVCDEC_ERROR_GREATER_THAN_1200_AT_LV30
C0-9227-0	0x80802013	SCE_APPMGR_ERROR_STATE
C0-9228-1	0x80803000	SCE_APPMGR_ERROR_BGM_PORT_BUSY
NP-9527-3	0x80550c40	SCE_NP_MATCHING2_SERVER_ERROR_SESSION_NOT_FOUND
NP-9528-4	0x80550d01	SCE_NP_MATCHING2_SERVER_ERROR_BAD_REQUEST
NP-9529-5	0x80550d02	SCE_NP_MATCHING2_SERVER_ERROR_SERVICE_UNAVAILABLE
NP-9530-7	0x80550d03	SCE_NP_MATCHING2_SERVER_ERROR_BUSY
NP-9531-8	0x80550d04	SCE_NP_MATCHING2_SERVER_ERROR_END_OF_SERVICE
NP-9532-9	0x80550d05	SCE_NP_MATCHING2_SERVER_ERROR_INTERNAL_SERVER_ERROR
NP-9533-0	0x80550d06	SCE_NP_MATCHING2_SERVER_ERROR_PLAYER_BANNED
NP-9534-1	0x80550d07	SCE_NP_MATCHING2_SERVER_ERROR_FORBIDDEN
NP-9535-2	0x80550d08	SCE_NP_MATCHING2_SERVER_ERROR_BLOCKED
NP-9536-3	0x80550d09	SCE_NP_MATCHING2_SERVER_ERROR_UNSUPPORTED_NP_ENV
NP-9537-4	0x80550d0a	SCE_NP_MATCHING2_SERVER_ERROR_INVALID_TICKET
NP-9538-5	0x80550d0b	SCE_NP_MATCHING2_SERVER_ERROR_INVALID_SIGNATURE
NP-9539-6	0x80550d0c	SCE_NP_MATCHING2_SERVER_ERROR_EXPIRED_TICKET
NP-9540-8	0x80550d0d	SCE_NP_MATCHING2_SERVER_ERROR_ENTITLEMENT_REQUIRED
NP-9541-9	0x80550d0e	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_CONTEXT
NP-9542-0	0x80550d0f	SCE_NP_MATCHING2_SERVER_ERROR_CLOSED
NP-9543-1	0x80550d10	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_TITLE
NP-9544-2	0x80550d11	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_WORLD
NP-9545-3	0x80550d12	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_LOBBY
NP-9546-4	0x80550d13	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_ROOM
NP-9547-5	0x80550d14	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_LOBBY_INSTANCE
NP-9548-6	0x80550d15	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_ROOM_INSTANCE
NP-9549-7	0x80550d17	SCE_NP_MATCHING2_SERVER_ERROR_PASSWORD_MISMATCH
NP-9550-9	0x80550d18	SCE_NP_MATCHING2_SERVER_ERROR_LOBBY_FULL
NP-9551-0	0x80550d19	SCE_NP_MATCHING2_SERVER_ERROR_ROOM_FULL
NP-9552-1	0x80550d1b	SCE_NP_MATCHING2_SERVER_ERROR_GROUP_FULL
NP-9553-2	0x80550d1c	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_USER
NP-9554-3	0x80550d1e	SCE_NP_MATCHING2_SERVER_ERROR_TITLE_PASSPHRASE_MISMATCH
NP-9555-4	0x80550d28	SCE_NP_MATCHING2_SERVER_ERROR_CONSOLE_BANNED
NP-9556-5	0x80550d29	SCE_NP_MATCHING2_SERVER_ERROR_NO_ROOMGROUP
NP-9557-6	0x80550d2a	SCE_NP_MATCHING2_SERVER_ERROR_NO_SUCH_GROUP
NP-9558-7	0x80550d2b	SCE_NP_MATCHING2_SERVER_ERROR_NO_PASSWORD
NP-9559-8	0x80550d2c	SCE_NP_MATCHING2_SERVER_ERROR_INVALID_GROUP_SLOT_NUMBER

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-9560-0	0x80550d2d	SCE_NP_MATCHING2_SERVER_ERROR_INVALID_PASSWORD_SLOT_MASK
NP-9561-1	0x80550d2e	SCE_NP_MATCHING2_SERVER_ERROR_DUPLICATE_GROUP_LABEL
NP-9562-2	0x80550d2f	SCE_NP_MATCHING2_SERVER_ERROR_REQUEST_OVERFLOW
NP-9563-3	0x80550d30	SCE_NP_MATCHING2_SERVER_ERROR_ALREADY_JOINED
NP-9564-4	0x80550d31	SCE_NP_MATCHING2_SERVER_ERROR_NAT_TYPE_MISMATCH
NP-9565-5	0x80550d32	SCE_NP_MATCHING2_SERVER_ERROR_ROOM_INCONSISTENCY
NP-9568-8	0x80550e01	SCE_NP_MATCHING2_SIGNALING_ERROR_NOT_INITIALIZED
NP-9569-9	0x80550e02	SCE_NP_MATCHING2_SIGNALING_ERROR_ALREADY_INITIALIZE_D
NP-9570-1	0x80550e03	SCE_NP_MATCHING2_SIGNALING_ERROR_OUT_OF_MEMORY
NP-9571-2	0x80550e04	SCE_NP_MATCHING2_SIGNALING_ERROR_CTXID_NOT_AVAILABLE
NP-9572-3	0x80550e05	SCE_NP_MATCHING2_SIGNALING_ERROR_CTX_NOT_FOUND
NP-9573-4	0x80550e06	SCE_NP_MATCHING2_SIGNALING_ERROR_REQID_NOT_AVAILABLE
NP-9574-5	0x80550e07	SCE_NP_MATCHING2_SIGNALING_ERROR_REQ_NOT_FOUND
NP-9575-6	0x80550e08	SCE_NP_MATCHING2_SIGNALING_ERROR_PARSER_CREATE_FAILED
NP-9576-7	0x80550e09	SCE_NP_MATCHING2_SIGNALING_ERROR_PARSER_FAILED
NP-9577-8	0x80550e0a	SCE_NP_MATCHING2_SIGNALING_ERROR_INVALID_NAMESPACE
NP-9578-9	0x80550e0b	SCE_NP_MATCHING2_SIGNALING_ERROR_NETINFO_NOT_AVAILABLE
NP-9579-0	0x80550e0c	SCE_NP_MATCHING2_SIGNALING_ERROR_PEER_NOT_RESPONDING
NP-9580-2	0x80550e0d	SCE_NP_MATCHING2_SIGNALING_ERROR_CONNID_NOT_AVAILABLE
NP-9581-3	0x80550e0e	SCE_NP_MATCHING2_SIGNALING_ERROR_CONN_NOT_FOUND
NP-9582-4	0x80550e0f	SCE_NP_MATCHING2_SIGNALING_ERROR_PEER_UNREACHABLE
NP-9583-5	0x80550e10	SCE_NP_MATCHING2_SIGNALING_ERROR_TERMINATED_BY_PEER
NP-9584-6	0x80550e11	SCE_NP_MATCHING2_SIGNALING_ERROR_TIMEOUT
NP-9585-7	0x80550e12	SCE_NP_MATCHING2_SIGNALING_ERROR_CTX_MAX
NP-9586-8	0x80550e13	SCE_NP_MATCHING2_SIGNALING_ERROR_RESULT_NOT_FOUND
NP-9587-9	0x80550e14	SCE_NP_MATCHING2_SIGNALING_ERROR_CONN_IN_PROGRESS
NP-9588-0	0x80550e15	SCE_NP_MATCHING2_SIGNALING_ERROR_INVALID_ARGUMENT
NP-9589-1	0x80550e16	SCE_NP_MATCHING2_SIGNALING_ERROR_OWN_NP_ID
NP-9590-3	0x80550e17	SCE_NP_MATCHING2_SIGNALING_ERROR_TOO_MANY_CONN
NP-9591-4	0x80550e18	SCE_NP_MATCHING2_SIGNALING_ERROR_TERMINATED_BY_MYSELF
NP-9592-5	0x80550e19	SCE_NP_MATCHING2_SIGNALING_ERROR_MATCHING2_PEER_NOT_FOUND
C4-9637-5	0x80290007	SCE_DISPLAY_ERROR_NO_FRAME_BUFFER
C4-9638-6	0x80290008	SCE_DISPLAY_ERROR_NO_PIXEL_DATA
C0-9639-7	0x805b0017	SCE_GXM_ERROR_DRIVER
C1-9640-9	0x8002000b	SCE_KERNEL_ERROR_ILLEGAL_SIZE
C1-9641-0	0x80024b07	SCE_KERNEL_ERROR_MEMBLOCK_TYPE_FOR_KERNEL_PROCESS
C1-9642-1	0x80024b08	SCE_KERNEL_ERROR_PROCESS_CANNOT_REMAP_MEMBLOCK
C1-9646-5	0x80029008	SCE_KERNEL_ERROR_CP14_DISABLED
C1-9647-6	0x80029009	SCE_KERNEL_ERROR_EXCEEDED_MAX_PROCESSES
C1-9648-7	0x8002d018	SCE_KERNEL_ERROR_MODULEMGR_CANNOT_EXPORT_LIB_TO_SHARED
C1-9649-8	0x8002d019	SCE_KERNEL_ERROR_MODULEMGR_INVALID_REL_INFO
C1-9650-0	0x8002d01a	SCE_KERNEL_ERROR_MODULEMGR_INVALID_REF_INFO
C1-9651-1	0x8002d01b	SCE_KERNEL_ERROR_MODULEMGR_ELINK
C1-9652-2	0x8002d01c	SCE_KERNEL_ERROR_MODULEMGR_NOENT
C1-9653-3	0x8002d01d	SCE_KERNEL_ERROR_MODULEMGR_BUSY
C1-9654-4	0x8002d01e	SCE_KERNEL_ERROR_MODULEMGR_NOEXEC

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-9655-5	0x8002d01f	SCE_KERNEL_ERROR_MODULEMGR_NAMETOOLONG
C0-9656-6	0x80560104	SCE_DEFLATE_ERROR_INVALID_CBINFO
NW-9657-7	0x80435026	SCE_SSL_ERROR_INTERNAL
NW-9658-8	0x80435025	SCE_SSL_ERROR_NOT_FOUND
NW-9659-9	0x804351fe	SCE_SSL_ERROR_INVALID_VALUE
NW-9660-1	0x80435108	SCE_SSL_ERROR_INVALID_FORMAT
NW-9661-2	0x804101a2	SCE_NET_ERROR_ERESUME
C0-9662-3	0x804e0901	SCE_VOICE_ERROR_LIBVOICEQOS_NOT_INIT
C0-9663-4	0x804e0902	SCE_VOICE_ERROR_LIBVOICEQOS_ARGUMENT_INVALID
C0-9664-5	0x804e0903	SCE_VOICE_ERROR_LIBVOICEQOS_PACKET_INVALID
C0-9665-6	0x804e0904	SCE_VOICE_ERROR_LIBVOICEQOS_INTERNAL_UNRECOVERABLE
C0-9666-7	0x804e0905	SCE_VOICE_ERROR_LIBVOICEQOS_INITIALIZED
C0-9667-8	0x804e0906	SCE_VOICE_ERROR_LIBVOICEQOS_SYSTEM
C0-9668-9	0x804e0907	SCE_VOICE_ERROR_LIBVOICEQOS_RESOURCE_USED
C0-9669-0	0x804e0801	SCE_VOICE_ERROR_LIBVOICE_NOT_INIT
C0-9670-2	0x804e0802	SCE_VOICE_ERROR_LIBVOICE_INITIALIZED
C0-9671-3	0x804e0803	SCE_VOICE_ERROR_GENERAL
C0-9672-4	0x804e0804	SCE_VOICE_ERROR_PORT_INVALID
C0-9673-5	0x804e0805	SCE_VOICE_ERROR_ARGUMENT_INVALID
C0-9674-6	0x804e0806	SCE_VOICE_ERROR_CONTAINER_INVALID
C0-9675-7	0x804e0807	SCE_VOICE_ERROR_TOPOLOGY
C0-9676-8	0x804e0808	SCE_VOICE_ERROR_RESOURCE_INSUFFICIENT
C0-9677-9	0x804e0809	SCE_VOICE_ERROR_NOT_IMPLEMENTED
C0-9678-0	0x804e080a	SCE_VOICE_ERROR_SERVICE_DETACHED
C0-9679-1	0x804e080b	SCE_VOICE_ERROR_SERVICE_ATTACHED
NP-9702-8	0x80551e01	SCE_NP_MESSAGE_ERROR_ALREADY_INITIALIZED
NP-9703-9	0x80551e02	SCE_NP_MESSAGE_ERROR_NOT_INITIALIZED
NP-9704-0	0x80551e03	SCE_NP_MESSAGE_ERROR_INVALID_ARGUMENT
NP-9705-1	0x80551e04	SCE_NP_MESSAGE_ERROR_ABORTED
NP-9706-2	0x80551e05	SCE_NP_MESSAGE_ERROR_OUT_OF_MEMORY
NP-9707-3	0x80551e06	SCE_NP_MESSAGE_ERROR_COULD_NOT_CONNECT_TO_SERVER
NP-9708-4	0x80551e07	SCE_NP_MESSAGE_ERROR_INTERNAL
C2-9729-7	0x80100605	SCE_APPUTIL_ERROR_NO_PERMISSION
C1-9730-9	0x80020406	SCE_COMMON_DIALOG_ERROR_ILLEGAL_CALLER_THREAD
C1-9731-0	0x80020421	SCE_COMMON_DIALOG_ERROR_INVALID_SURFACE_RESOLUTION
C1-9732-1	0x80020422	SCE_COMMON_DIALOG_ERROR_INVALID_SURFACE_STRIDE
NW-9733-2	0x80436001	SCE_HTTP_ERROR_RESOLVER_EPACKET
NW-9734-3	0x80436002	SCE_HTTP_ERROR_RESOLVER_ENODNS
NW-9735-4	0x80436003	SCE_HTTP_ERROR_RESOLVER_ETIMEDOUT
NW-9736-5	0x80436004	SCE_HTTP_ERROR_RESOLVER_ENOSUPPORT
NW-9737-6	0x80436005	SCE_HTTP_ERROR_RESOLVER_EFORMAT
NW-9738-7	0x80436006	SCE_HTTP_ERROR_RESOLVER_ESERVERFAILURE
NW-9739-8	0x80436007	SCE_HTTP_ERROR_RESOLVER_ENOHOST
NW-9740-0	0x80436008	SCE_HTTP_ERROR_RESOLVER_ENOTIMPLEMENTED
NW-9741-1	0x80436009	SCE_HTTP_ERROR_RESOLVER_ESERVERREFUSED
NW-9742-2	0x8043600a	SCE_HTTP_ERROR_RESOLVER_ENORECORD
NW-9743-3	0x80435060	SCE_HTTPS_ERROR_CERT
NW-9744-4	0x80435061	SCE_HTTPS_ERROR_HANDSHAKE
NW-9745-5	0x80435062	SCE_HTTPS_ERROR_IO
NW-9746-6	0x80435063	SCE_HTTPS_ERROR_INTERNAL
NW-9747-7	0x80435064	SCE_HTTPS_ERROR_PROXY
C2-9748-8	0x80100c03	SCE_NETCHECK_DIALOG_ERROR_LACK_OF_LIBHTTP_POOL_SIZE
C2-9749-9	0x80100c04	SCE_NETCHECK_DIALOG_ERROR_LACK_OF_LIBSSL_POOL_SIZE
NP-9750-1	0x80551d01	SCE_NP_BASIC_ERROR_UNKNOWN
NP-9751-2	0x80551d02	SCE_NP_BASIC_ERROR_INVALID_ARGUMENT
NP-9752-3	0x80551d03	SCE_NP_BASIC_ERROR_OUT_OF_MEMORY
NP-9753-4	0x80551d04	SCE_NP_BASIC_ERROR_NOT_INITIALIZED

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-9754-5	0x80551d05	SCE NP BASIC ERROR ALREADY INITIALIZED
NP-9755-6	0x80551d06	SCE NP BASIC ERROR SIGNED_OUT
NP-9756-7	0x80551d07	SCE NP BASIC ERROR NOT ONLINE
NP-9757-8	0x80551d08	SCE NP BASIC ERROR DATA NOT FOUND
NP-9758-9	0x80551d09	SCE NP BASIC ERROR BUSY
NP-9759-0	0x80551d0a	SCE NP BASIC ERROR NOT READY TO COMMUNICATE
NP-9760-2	0x80551d0b	SCE NP BASIC ERROR NO COMM ID SUPPLIED
NP-9761-3	0x80550403	SCE NP AUTH ERROR SERVER MAINTENANCE
NP-9763-5	0x805508aa	SCE NP COMMUNITY_SERVER_ERROR_TITLE_USER_STORAGE_BEFORE SERVICE
NP-9764-6	0x805508ab	SCE NP COMMUNITY_SERVER_ERROR_TITLE_USER_STORAGE_END OF SERVICE
NP-9765-7	0x805508ac	SCE NP COMMUNITY_SERVER_ERROR_TITLE_USER_STORAGE_MAINTENANCE
NP-9766-8	0x805508ad	SCE NP COMMUNITY_SERVER_ERROR_FSR_BEFORE SERVICE
NP-9767-9	0x805508ae	SCE NP COMMUNITY_SERVER_ERROR_FSR_END OF SERVICE
NP-9768-0	0x805508af	SCE NP COMMUNITY_SERVER_ERROR_FSR MAINTENANCE
NP-9769-1	0x805508b1	SCE NP COMMUNITY_SERVER_ERROR_UBS_END OF SERVICE
NP-9770-3	0x805508b2	SCE NP COMMUNITY_SERVER_ERROR_UBS MAINTENANCE
NP-9771-4	0x805508b3	SCE NP COMMUNITY_SERVER_ERROR_BASIC_BLACKLISTED_USER ID
NP-9772-5	0x80551f01	SCE NP BANDWIDTH TEST ERROR ALREADY INITIALIZED
NP-9773-6	0x80551f02	SCE NP BANDWIDTH TEST ERROR NOT INITIALIZED
NP-9774-7	0x80551f03	SCE NP BANDWIDTH TEST ERROR BAD RESPONSE
NP-9775-8	0x80551f04	SCE NP BANDWIDTH TEST ERROR HTTP POOL TOO SHORT
C2-9776-9	0x80101f01	SCE NP PROFILE_DIALOG_ERROR_INVALID PARAM
C2-9777-0	0x80101f02	SCE NP_PROFILE_DIALOG_ERROR_REQUIRED_MODULES_NOT_LOADED
C2-9778-1	0x80101f03	SCE NP PROFILE_DIALOG_ERROR_NOT SIGNED IN
C2-9779-2	0x80102601	SCE NP_TROPHY_SETUP_DIALOG_ERROR_PARAM
C2-9781-5	0x80102201	SCE STORE_CHECKOUT_DIALOG_ERROR_INTERNAL
C2-9782-6	0x80102202	SCE STORE_CHECKOUT_DIALOG_ERROR_PARAM
C2-9783-7	0x80102203	SCE STORE_CHECKOUT_DIALOG_ERROR_NP
C2-9881-6	0x80100643	SCE APPUTIL_ERROR_SAVEDATA_NO_SPACE_FS
C0-10259-7	0x80802016	SCE APPMGR_ERROR_NULL_POINTER
C0-10261-0	0x8080201a	SCE APPMGR_ERROR_INVALID
C0-10263-2	0x8080201c	SCE APP_MGR_ERROR_PERMISSION
C4-10266-5	0x802e0011	SCE CAMERA_ERROR_DATA_RANGE_UNKNOWN
C4-10299-1	0x802b0003	SCE POWER_ERROR_CANT_SUSPEND
C0-10307-1	0x80820020	SCE_FIOS_ERROR_BAD_RESOLVE_TYPE SCE_FIOS_KERNEL_ERROR_BAD_RESOLVE_TYPE
C0-10308-2	0x80481001	SCE HMAC_ERROR_INVALID_STATE
C0-10309-3	0x80481002	SCE HMAC_ERROR_INVALID_DIGEST_SIZE
C4-10655-7	0x8026010a	SCE_AUDIO_IN_ERROR_BUSY
C0-10656-8	0x80600001	SCE_CODECENGINE_ERROR_INVALID_SIZE
C0-10657-9	0x805b0018	SCE_GXM_ERROR_INVALID_THREAD
C1-10658-0	0x8002000c	SCE_KERNEL_ERROR_ILLEGAL_TYPE
C1-10659-1	0x8002000d	SCE_KERNEL_ERROR_ILLEGAL_PATTERN
C1-10660-3	0x8002000e	SCE_KERNEL_ERROR_ILLEGAL_ATTR
C1-10661-4	0x80024307	SCE_KERNEL_ERROR_PHYMEMPART_OUT_OF_INDEX
C1-10662-5	0x8002450b	SCE_KERNEL_ERROR_UID_NOT_VISIBLE
C1-10663-6	0x80024e00	SCE_KERNEL_ERROR_SYSMEM_NAMEHEAP_ERROR
C1-10664-7	0x80024e01	SCE_KERNEL_ERROR_NO_SUCH_NAME
C1-10665-8	0x80024e02	SCE_KERNEL_ERROR_DUPLICATE_NAME
C1-10672-6	0x8002900a	SCE_KERNEL_ERROR_PROCESS_REMAINING
C0-10673-7	0x804f0001	SCE_HEAP_ERROR_INVALID_POINTER
C0-10674-8	0x80480800	SCE_SHA512T_ERROR_INVALID_POINTER

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-10675-9	0x80480801	SCE_SHA512T_ERROR_INVALID_STATE
C0-10676-0	0x80480802	SCE_SHA512T_ERROR_INVALID_DIGEST_SIZE
C4-10677-1	0x8036020a	SCE_POS_MOTION_ERROR_ANGLE_OUT_OF_RANGE SCE_MOTION_ERROR_ANGLE_OUT_OF_RANGE
NW-10678-2	0x804101a3	SCE_NET_ERROR_EIPADDRCHANGED SCE_NET_ERROR_EINACTIV EDISABLED
C1-10679-3	0x8008c000	SCE_RAZOR_GPU_ERROR_NOT_INITIALIZED
C1-10680-5	0x8008c001	SCE_RAZOR_GPU_ERROR_INVALID_ARGUMENT
C1-10681-6	0x8008c002	SCE_RAZOR_GPU_ERROR_INVALID_PERF_MODE
C1-10682-7	0x8008c003	SCE_RAZOR_GPU_ERROR_LIVE_NOT_STARTED
C1-10683-8	0x8008c004	SCE_RAZOR_GPU_ERROR_LIVE_ALREADY_STARTED
C1-10684-9	0x8008c005	SCE_RAZOR_GPU_ERROR_PA_NOT_AVAILABLE
C1-10685-0	0x8008c006	SCE_RAZOR_GPU_ERROR_TRACE_OVERFLOW
C1-10686-1	0x8008c007	SCE_RAZOR_GPU_ERROR_NOT_ALIGNED
C0-10687-2	0x80650067	SCE_JPEG_ERROR_INVALID_INIT_PARAM
C0-10688-3	0x80650207	SCE_JPEGENC_ERROR_INVALID_INIT_PARAM
NW-10702-0	0x80413101	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_MODE
NW-10703-1	0x80413102	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_PORT
NW-10704-2	0x80413103	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_MAXNUM
NW-10705-3	0x80413104	SCE_NET_ADHOC_MATCHING_ERROR_RXBUF_TOO_SHORT
NW-10706-4	0x80413105	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_OPTLEN
NW-10707-5	0x80413106	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_ARG
NW-10708-6	0x80413107	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_ID
NW-10709-7	0x80413108	SCE_NET_ADHOC_MATCHING_ERROR_ID_NOT_AVAIL
NW-10710-9	0x80413109	SCE_NET_ADHOC_MATCHING_ERROR_NO_SPACE
NW-10711-0	0x8041310a	SCE_NET_ADHOC_MATCHING_ERROR_IS_RUNNING
NW-10712-1	0x8041310b	SCE_NET_ADHOC_MATCHING_ERROR_NOT_RUNNING
NW-10713-2	0x8041310c	SCE_NET_ADHOC_MATCHING_ERROR_UNKNOWN_TARGET
NW-10714-3	0x8041310d	SCE_NET_ADHOC_MATCHING_ERROR_TARGET_NOT_READY
NW-10715-4	0x8041310e	SCE_NET_ADHOC_MATCHING_ERROR_EXCEED_MAXNUM
NW-10716-5	0x8041310f	SCE_NET_ADHOC_MATCHING_ERROR_REQUEST_IN_PROGRESS
NW-10717-6	0x80413110	SCE_NET_ADHOC_MATCHING_ERROR_ALREADY_ESTABLISHED
NW-10718-7	0x80413111	SCE_NET_ADHOC_MATCHING_ERROR_BUSY
NW-10719-8	0x80413112	SCE_NET_ADHOC_MATCHING_ERROR_ALREADY_INITIALIZED
NW-10720-0	0x80413113	SCE_NET_ADHOC_MATCHING_ERROR_NOT_INITIALIZED
NW-10721-1	0x80413114	SCE_NET_ADHOC_MATCHING_ERROR_PORT_IN_USE
NW-10722-2	0x80413115	SCE_NET_ADHOC_MATCHING_ERROR_STACKSIZE_TOO_SHORT
NW-10723-3	0x80413116	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_DATALEN
NW-10724-4	0x80413117	SCE_NET_ADHOC_MATCHING_ERROR_NOT_ESTABLISHED
NW-10725-5	0x80413118	SCE_NET_ADHOC_MATCHING_ERROR_DATA_BUSY
NW-10726-6	0x80413119	SCE_NET_ADHOC_MATCHING_ERROR_INVALID_ALIGNMENT
C2-10727-7	0x80100620	SCE_APPUTIL_ERROR_APPEVENT_PARSE_INVALID_DATA
C2-10728-8	0x80104701	SCE_CAMERAIMPORT_DIALOG_ERROR_CAMERA_ALREADY_USED
C2-10729-9	0x80104702	SCE_CAMERAIMPORT_DIALOG_ERROR_INVALID_WORKING_BUFFER
C2-10730-1	0x80104703	SCE_CAMERAIMPORT_DIALOG_ERROR_REQUIRED_PRX_IS_NOT_LOADED
C2-10731-2	0x80104704	SCE_CAMERAIMPORT_DIALOG_ERROR_REQUIRED_DEVICE_CANNOT_USE
C2-10732-3	0x80104600	SCE_CLIPBOARD_ERROR_INTERNAL
C2-10733-4	0x80104601	SCE_CLIPBOARD_ERROR_NULL_POINTER
C2-10734-5	0x80104602	SCE_CLIPBOARD_ERROR_TEXT_TOO_LONG
C2-10735-6	0x80104603	SCE_CLIPBOARD_ERROR_UNSUPPORTED_CHARACTER
C1-10736-7	0x80020407	SCE_COMMON_DIALOG_ERROR_NOT_CONFIGURED
C1-10737-8	0x80020423	SCE_COMMON_DIALOG_ERROR_INVALID_SURFACE_TYPE
C1-10738-9	0x80020431	SCE_COMMON_DIALOG_ERROR_INVALID_LANGUAGE
C1-10739-0	0x80020432	SCE_COMMON_DIALOG_ERROR_INVALID_ENTER_BUTTON_ASSIGN

©SCEI



SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-10740-2	0x80102003	SCE_IME_DIALOG_ERROR_INVALID_DIALOG_MODE
C2-10741-3	0x80102004	SCE_IME_DIALOG_ERROR_INVALID_TEXT_BOX_MODE
C2-10742-4	0x80102005	SCE_IME_DIALOG_ERROR_INVALID_TITLE
NW-10743-5	0x80431084	SCE_HTTP_ERROR_PROXY
C2-10745-7	0x80100706	SCE_IME_ERROR_INVALID_TEXT
C2-10746-8	0x80100710	SCE_IME_ERROR_INVALID_SIZE
C2-10748-0	0x80100712	SCE_IME_ERROR_INVALID_INPUT_METHOD
C2-10749-1	0x80100713	SCE_IME_ERROR_INVALID_SUPPORTED_LANGUAGES
C2-10750-3	0x80100714	SCE_IME_ERROR_INVALID_TYPE
C2-10751-4	0x80100715	SCE_IME_ERROR_INVALID_OPTION
C2-10752-5	0x80100716	SCE_IME_ERROR_INVALID_WORK
C2-10753-6	0x80100717	SCE_IME_ERROR_INVALID_ARG
C2-10754-7	0x80100718	SCE_IME_ERROR_INVALID_HANDLER
C2-10755-8	0x80100719	SCE_IME_ERROR_INVALID_MAX_TEXT_LENGTH
C2-10756-9	0x8010071a	SCE_IME_ERROR_INVALID_INPUT_TEXT_BUFFER
C2-10757-0	0x8010071b	SCE_IME_ERROR_INVALID_RESERVED
NW-10758-1	0x80412112	SCE_NET_CTL_ERROR_FLIGHT_MODE_ENABLED
NW-10759-2	0x80412113	SCE_NET_CTL_ERROR_WIFI_DISABLED
NW-10760-4	0x80412114	SCE_NET_CTL_ERROR_WIFI_IN_ADHOC_USE
NW-10761-5	0x80412115	SCE_NET_CTL_ERROR_ETHERNET_PLUGOUT
C2-10762-6	0x80104001	SCE_LIVEAREA_ERROR_STATE
C2-10763-7	0x80104002	SCE_LIVEAREA_ERROR_PARAM
C2-10764-8	0x80104003	SCE_LIVEAREA_ERROR_XML_NOT_FOUND
C2-10765-9	0x80104004	SCE_LIVEAREA_ERROR_XML_FORMAT
C2-10766-0	0x80104005	SCE_LIVEAREA_ERROR_FILE_NOT_FOUND
C2-10767-1	0x80104006	SCE_LIVEAREA_ERROR_FILE_NUM
C2-10768-2	0x80104007	SCE_LIVEAREA_ERROR_FILE_TOTAL_SIZE
C2-10769-3	0x80104008	SCE_LIVEAREA_ERROR_FILE_FORMAT
C2-10770-5	0x80104009	SCE_LIVEAREA_ERROR_XML_SIZE
C2-10771-6	0x8010400a	SCE_LIVEAREA_ERROR_FRAME_NOT_FOUND
C2-10772-7	0x801040ff	SCE_LIVEAREA_ERROR_INTERNAL
C2-10773-8	0x80104901	SCE_NEAR_ERROR_INVALID_ARGUMENT
C2-10774-9	0x80104902	SCE_NEAR_ERROR_INVALID_COMMUNICATION_ID
C2-10775-0	0x80104903	SCE_NEAR_ERROR_ALREADY_INITIALIZED
C2-10776-1	0x80104904	SCE_NEAR_ERROR_NO_MEMORY
C2-10777-2	0x80104905	SCE_NEAR_ERROR_NOT_INITIALIZED
C2-10778-3	0x80104906	SCE_NEAR_ERROR_INVALID_GIFT_INFO
C2-10779-4	0x80104907	SCE_NEAR_ERROR_IMAGE_SIZE_OVER
C2-10780-6	0x80104908	SCE_NEAR_ERROR_DATA_SIZE_OVER
C2-10781-7	0x80104909	SCE_NEAR_ERROR_GIFT_COUNT
C2-10782-8	0x8010490a	SCE_NEAR_ERROR_INVALID_CONDITION
C2-10790-7	0x80104912	SCE_NEAR_ERROR_RETRIEVE_FAILED
C2-10791-8	0x80104913	SCE_NEAR_ERROR_IMAGE_RETRIEVE_FAILED
C2-10792-9	0x80104914	SCE_NEAR_ERROR_DATA_RETRIEVE_FAILED
C2-10794-1	0x80104916	SCE_NEAR_ERROR_FILE_OPEN_NUM
C2-10796-3	0x80104918	SCE_NEAR_ERROR_DELETION_FAILED
C2-10797-4	0x80104919	SCE_NEAR_ERROR_NOT_RECEIVED
C2-10798-5	0x8010491a	SCE_NEAR_ERROR_EXPIRED
C2-10799-6	0x8010491b	SCE_NEAR_ERROR_FILE_NOT_OPENED
C2-10801-0	0x8010491d	SCE_NEAR_ERROR_FILE_BAD_OFFSET
C2-10802-1	0x8010491e	SCE_NEAR_ERROR_NOT_RETRIEVED
NP-10803-2	0x80550717	SCE_NP_COMMUNITY_ERROR_REQUEST_BEFORE_END
NP-10804-3	0x80550f70	SCE_NP_COMMERCE2_ERROR_HTTP_POOL_TOO_SHORT
NP-10805-4	0x80550f71	SCE_NP_COMMERCE2_ERROR_SSL_POOL_TOO_SHORT
NP-10806-5	0x80550fe1	SCE_NP_COMMERCE2_SC_ERROR_INVALID_RESPONSE
NP-10807-6	0x80552301	SCE_NP_ACTIVITY_ERROR_ALREADY_INITIALIZED
NP-10808-7	0x80552302	SCE_NP_ACTIVITY_ERROR_NOT_INITIALIZED

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-10809-8	0x80552303	SCE NP ACTIVITY_ERROR_INVALID_ARGUMENT
NP-10810-0	0x80552304	SCE NP ACTIVITY_ERROR_INVALID_URI_SCHEME
NP-10811-1	0x80552305	SCE NP ACTIVITY_ERROR_INVALID_STATUS_MESSAGE
NP-10812-2	0x80552501	SCE NP PARTY_ERROR_UNKNOWN
NP-10813-3	0x80552502	SCE NP PARTY_ERROR_ALREADY_INITIALIZED
NP-10814-4	0x80552503	SCE NP PARTY_ERROR_NOT_INITIALIZED
NP-10815-5	0x80552504	SCE NP PARTY_ERROR_INVALID_ARGUMENT
NP-10816-6	0x80552505	SCE NP PARTY_ERROR_OUT_OF_MEMORY
NP-10817-7	0x80552506	SCE NP PARTY_ERROR_NOT_IN_PARTY
C2-10818-8	0x80103701	SCE PHOTOREVIEW_DIALOG_ERROR_DECODE
C2-10819-9	0x80103702	SCE PHOTOREVIEW_DIALOG_ERROR_NO_SPACE
C2-10820-1	0x80103703	SCE PHOTOREVIEW_DIALOG_ERROR_REGISTRATION
C2-10821-2	0x80103704	SCE PHOTOREVIEW_DIALOG_ERROR_INTERNAL
C2-10822-3	0x80103705	SCE PHOTOREVIEW_DIALOG_ERROR_UNSUPPORTED_FILE
C2-10823-4	0x80103706	SCE PHOTOREVIEW_DIALOG_ERROR_FILE_CORRUPTED
C2-10824-5	0x80103707	SCE PHOTOREVIEW_DIALOG_ERROR_MEMORY
C2-10825-6	0x80101a01	SCE PHOTO_EXPORT_ERROR_PARAM
C2-10826-7	0x80101a02	SCE PHOTO_EXPORT_ERROR_FILE_NOT_FOUND
C2-10827-8	0x80101a03	SCE PHOTO_EXPORT_ERROR_CONTENT_FULL
C2-10828-9	0x80101a04	SCE PHOTO_EXPORT_ERROR_NO_MEMORY
C2-10829-0	0x80101a05	SCE PHOTO_EXPORT_ERROR_SERVER_DOWN
C2-10830-2	0x80101a06	SCE PHOTO_EXPORT_ERROR_TOO_MANY_CLIENT
C2-10831-3	0x80101a07	SCE PHOTO_EXPORT_ERROR_MEDIA_FULL
C2-10832-4	0x80101a08	SCE PHOTO_EXPORT_ERROR_CREATE_FILE
C2-10833-5	0x80101a09	SCE PHOTO_EXPORT_ERROR_NOT_SUPPORTED_FORMAT
C2-10834-6	0x80101a0a	SCE PHOTO_EXPORT_ERROR_DECODE_FAILED
C2-10835-7	0x80101a0b	SCE PHOTO_EXPORT_ERROR_CANCELED
C2-10836-8	0x80101a0c	SCE PHOTO_EXPORT_ERROR_INTERNAL
C2-10837-9	0x80101a0d	SCE PHOTO_EXPORT_ERROR_MEDIA_NOT_EXIST
C2-10838-0	0x80101a0e	SCE PHOTO_EXPORT_ERROR_DB_CORRUPTED
C2-10839-1	0x80102f01	SCE SCREENSHOT_ERROR_INVALID_ARGUMENT
C2-10840-3	0x80102f02	SCE SCREENSHOT_ERROR_NO_MEMORY
C2-10841-4	0x80102f03	SCE SCREENSHOT_ERROR_FILE_NOT_FOUND
C2-10842-5	0x80102f04	SCE SCREENSHOT_ERROR_NOT_SUPPORTED_FORMAT
C2-10843-6	0x80102f05	SCE SCREENSHOT_ERROR_MEDIA_FULL
C2-10844-7	0x80102f06	SCE SCREENSHOT_ERROR_INTERNAL
C0-10845-8	0x80850001	SCE XML_ERROR_NO_MEMORY
C0-10846-9	0x80850002	SCE XML_ERROR_NOT_INITIALIZED
C0-10847-0	0x80850003	SCE XML_ERROR_INVALID_ARGUMENT
C0-10848-1	0x80850004	SCE XML_ERROR_NOT_SUPPORTED
C0-10849-2	0x80850005	SCE XML_ERROR_INITIALIZE_FAILED
C0-10850-4	0x80850006	SCE XML_ERROR_INVALID_BIN_XML
C0-10851-5	0x80850007	SCE XML_ERROR_PARSER_BUSY
C0-10852-6	0x80850008	SCE XML_ERROR_XML_UNEXPECTED_EOF
C0-10853-7	0x80850009	SCE XML_ERROR_XML_SYNTAX_ERROR
C0-10854-8	0x8085000a	SCE XML_ERROR_XML_END_TAG_MISMATCH
C0-10855-9	0x8085000b	SCE XML_ERROR_XML_INVALID_CHAR
C0-10856-0	0x8085000c	SCE XML_ERROR_XML_INVALID_DEC_VALUE
C0-10857-1	0x8085000d	SCE XML_ERROR_XML_INVALID_HEX_VALUE
C0-10858-2	0x8085000e	SCE_XML_ERROR_XML_CLOSING_ANGLE_BRACKET_CHAR_NOT_FOUND
C0-10859-3	0x8085000f	SCE XML_ERROR_XML_EQUALITY_CHAR_NOT_FOUND
C0-10860-5	0x80850010	SCE XML_ERROR_XML_SEMI_COLON_CHAR_NOT_FOUND
C0-10861-6	0x80850011	SCE XML_ERROR_XML_QUOTE_CHAR_NOT_FOUND
C0-10862-7	0x80850012	SCE XML_ERROR_XML_END_OF_COMMENT_NOT_FOUND
C0-10863-8	0x80850013	SCE XML_ERROR_XML_END_OF_CD_SECT_NOT_FOUND
C0-10864-9	0x80850014	SCE XML_ERROR_XML_END_OF_DTD_NOT_FOUND

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-10865-0	0x80850015	SCE_XML_ERROR_XML_UNKNOWN_ENCODING
C0-10866-1	0x80850016	SCE_XML_ERROR_XML_HANDLER_NOT_SET
C0-10867-2	0x80850017	SCE_XML_ERROR_XML_INVALID_PI
C0-10868-3	0x80850018	SCE_XML_ERROR_XML_INVALID_DOCUMENT_ELEMENT
C0-10869-4	0x80850019	SCE_XML_ERROR_XML_DOCUMENT_ELEMENT_NOT_FOUND
C0-10870-6	0x8085001a	SCE_XML_ERROR_XML_DUPLICATE_ATTR_NAME
C0-10871-7	0x80850200	SCE_XML_ERROR_DOM_ERROR
C0-10872-8	0x80850201	SCE_XML_ERROR_DOM_NODE_NOT_FOUND
C0-10873-9	0x80850202	SCE_XML_ERROR_DOM_READ_ONLY_ERROR
C0-10874-0	0x80850203	SCE_XML_ERROR_DOM_MAX_UNIQUE_ELEMENT_ERROR
C0-10875-1	0x80850204	SCE_XML_ERROR_DOM_MAX_UNIQUE_ATTR_ERROR
C0-10876-2	0x80850205	SCE_XML_ERROR_DOM_MAX_NUM_OF_ATTR_ERROR
C0-10877-3	0x80850206	SCE_XML_ERROR_DOM_MAX_SIZE_OF_ELEMENT_NAME_ERROR
C0-10878-4	0x80850207	SCE_XML_ERROR_DOM_MAX_SIZE_OF_ATTR_NAME_ERROR
C0-10879-5	0x80850208	SCE_XML_ERROR_DOM_MAX_SIZE_OF_ATTR_VALUE_ERROR
C0-10880-7	0x80850209	SCE_XML_ERROR_DOM_INVALID_ENTITY
C0-10881-8	0x8085020a	SCE_XML_ERROR_DOM_INVALID_NODE_TYPE
NW-10913-4	0x80412801	SCE_GAME_UPDATE_ERROR_NOT_INITIALIZED
NW-10914-5	0x80412802	SCE_GAME_UPDATE_ERROR_ALREADY_INITIALIZED
NW-10915-6	0x80412803	SCE_GAME_UPDATE_ERROR_INVALID_ARG
NW-10916-7	0x80412804	SCE_GAME_UPDATE_ERROR_HTTP_OUT_OF_MEMORY
NW-10917-8	0x80412805	SCE_GAME_UPDATE_ERROR_HTTP_LOCAL_ERROR
NW-10918-9	0x80412806	SCE_GAME_UPDATE_ERROR_HTTP_CONNECTION_ERROR
NW-10919-0	0x80412807	SCE_GAME_UPDATE_ERROR_HTTP_PROXY_ERROR
NW-10920-2	0x80412808	SCE_GAME_UPDATE_ERROR_HTTP_BAD_RESPONSE
NW-10921-3	0x80412809	SCE_GAME_UPDATE_ERROR_PARSER_FAILED
NW-10922-4	0x8041280a	SCE_GAME_UPDATE_ERROR_BAD_RESPONSE
NW-10923-5	0x8041280b	SCE_GAME_UPDATE_ERROR_BUSY
NW-10924-6	0x8041280c	SCE_GAME_UPDATE_ERROR_ABORTED
C4-11110-4	0x802e0012	SCE_CAMERA_ERROR_OTHER_ALREADY_START
NW-11116-0	0x80431085	SCE_HTTP_ERROR_BROKEN
C2-11117-1	0x80100707	SCE_IME_ERROR_TOO_MANY_REQUESTS
C1-11150-8	0x8002000f	SCE_KERNEL_ERROR_ILLEGAL_COUNT
C1-11151-9	0x80020010	SCE_KERNEL_ERROR_ILLEGAL_MODE
C1-11152-0	0x80028060	SCE_KERNEL_ERROR_THREAD_EVENT_ERROR
C1-11153-1	0x80028080	SCE_KERNEL_ERROR_KERNEL_TLS_ERROR
C1-11154-2	0x80028081	SCE_KERNEL_ERROR_KERNEL_TLS_FULL
C1-11155-3	0x80028082	SCE_KERNEL_ERROR_ILLEGAL_KERNEL_TLS_INDEX
C1-11156-4	0x80028083	SCE_KERNEL_ERROR_KERNEL_TLS_BUSY
C1-11157-5	0x800280a0	SCE_KERNEL_ERROR_CALLBACK_ERROR
C1-11158-6	0x800280a1	SCE_KERNEL_ERROR_UNKNOWN_CALLBACK_ID
C1-11159-7	0x800280a2	SCE_KERNEL_ERROR_NOTIFY_CALLBACK
C1-11160-9	0x800280c0	SCE_KERNEL_ERROR_ALARM_ERROR
C1-11161-0	0x800280c1	SCE_KERNEL_ERROR_UNKNOWN_ALARM_ID
C1-11162-1	0x800280c2	SCE_KERNEL_ERROR_ALARM_CAN_NOT_CANCEL
C1-11163-2	0x800280e0	SCE_KERNEL_ERROR_EVF_ERROR
C1-11164-3	0x800280e1	SCE_KERNEL_ERROR_UNKNOWN_EVF_ID
C1-11165-4	0x800280e2	SCE_KERNEL_ERROR_EVF_MULTI
C1-11166-5	0x800280e3	SCE_KERNEL_ERROR_EVF_COND
C1-11167-6	0x80028100	SCE_KERNEL_ERROR_SEMA_ERROR
C1-11168-7	0x80028101	SCE_KERNEL_ERROR_UNKNOWN_SEMA_ID
C1-11169-8	0x80028102	SCE_KERNEL_ERROR_SEMA_ZERO
C1-11170-0	0x80028103	SCE_KERNEL_ERROR_SEMA_OVF
C1-11171-1	0x80028120	SCE_KERNEL_ERROR_SIGNAL_ERROR
C1-11172-2	0x80028121	SCE_KERNEL_ERROR_ALREADY_SENT
C1-11173-3	0x80028140	SCE_KERNEL_ERROR_MUTEX_ERROR
C1-11174-4	0x80028141	SCE_KERNEL_ERROR_UNKNOWN_MUTEX_ID

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-11175-5	0x80028142	SCE_KERNEL_ERROR_MUTEX_RECURSIVE
C1-11176-6	0x80028143	SCE_KERNEL_ERROR_MUTEX_LOCK_OVF
C1-11177-7	0x80028144	SCE_KERNEL_ERROR_MUTEX_UNLOCK_UDF
C1-11178-8	0x80028145	SCE_KERNEL_ERROR_MUTEX_FAILED_TO_OWN
C1-11179-9	0x80028146	SCE_KERNEL_ERROR_MUTEX_NOT_OWNED
C1-11180-1	0x80028160	SCE_KERNEL_ERROR_FAST_MUTEX_ERROR
C1-11181-2	0x80028161	SCE_KERNEL_ERROR_UNKNOWN_FAST_MUTEX_ID
C1-11182-3	0x80028162	SCE_KERNEL_ERROR_FAST_MUTEX_RECURSIVE
C1-11183-4	0x80028163	SCE_KERNEL_ERROR_FAST_MUTEX_LOCK_OVF
C1-11184-5	0x80028164	SCE_KERNEL_ERROR_FAST_MUTEX_FAILED_TO_OWN
C1-11185-6	0x80028165	SCE_KERNEL_ERROR_FAST_MUTEX_NOT_OWNED
C1-11186-7	0x80028166	SCE_KERNEL_ERROR_FAST_MUTEX_OWNED
C1-11187-8	0x80028167	SCE_KERNEL_ERROR_FAST_MUTEX_ALREADY_INITIALIZED
C1-11188-9	0x80028180	SCE_KERNEL_ERROR_LW_MUTEX_ERROR
C1-11189-0	0x80028181	SCE_KERNEL_ERROR_UNKNOWN_LW_MUTEX_ID
C1-11190-2	0x80028182	SCE_KERNEL_ERROR_LW_MUTEX_RECURSIVE
C1-11191-3	0x80028183	SCE_KERNEL_ERROR_LW_MUTEX_LOCK_OVF
C1-11192-4	0x80028184	SCE_KERNEL_ERROR_LW_MUTEX_UNLOCK_UDF
C1-11193-5	0x80028185	SCE_KERNEL_ERROR_LW_MUTEX_FAILED_TO_OWN
C1-11194-6	0x80028186	SCE_KERNEL_ERROR_LW_MUTEX_NOT_OWNED
C1-11195-7	0x800281a0	SCE_KERNEL_ERROR_COND_ERROR
C1-11196-8	0x800281a1	SCE_KERNEL_ERROR_UNKNOWN_COND_ID
C1-11197-9	0x800281a2	SCE_KERNEL_ERROR_WAIT_DELETE_MUTEX
C1-11198-0	0x800281a3	SCE_KERNEL_ERROR_WAIT_CANCEL_MUTEX
C1-11199-1	0x800281a4	SCE_KERNEL_ERROR_WAIT_DELETE_COND
C1-11200-4	0x800281a5	SCE_KERNEL_ERROR_WAIT_CANCEL_COND
C1-11201-5	0x800281c0	SCE_KERNEL_ERROR_LW_COND_ERROR
C1-11202-6	0x800281c1	SCE_KERNEL_ERROR_UNKNOWN_LW_COND_ID
C1-11203-7	0x800281c2	SCE_KERNEL_ERROR_WAIT_DELETE_LW_MUTEX
C1-11204-8	0x800281e0	SCE_KERNEL_ERROR_RW_LOCK_ERROR
C1-11205-9	0x800281e1	SCE_KERNEL_ERROR_UNKNOWN_RW_LOCK_ID
C1-11206-0	0x800281e2	SCE_KERNEL_ERROR_RW_LOCK_RECURSIVE
C1-11207-1	0x800281e3	SCE_KERNEL_ERROR_RW_LOCK_LOCK_OVF
C1-11208-2	0x800281e4	SCE_KERNEL_ERROR_RW_LOCK_NOT_OWNED
C1-11209-3	0x800281e5	SCE_KERNEL_ERROR_RW_LOCK_UNLOCK_UDF
C1-11210-5	0x800281e6	SCE_KERNEL_ERROR_RW_LOCK_FAILED_TO_LOCK
C1-11211-6	0x800281e7	SCE_KERNEL_ERROR_RW_LOCK_FAILED_TO_UNLOCK
C1-11212-7	0x80028200	SCE_KERNEL_ERROR_EVENT_ERROR
C1-11213-8	0x80028201	SCE_KERNEL_ERROR_UNKNOWN_EVENT_ID
C1-11214-9	0x80028202	SCE_KERNEL_ERROR_EVENT_COND
C1-11215-0	0x80028220	SCE_KERNEL_ERROR_MSG_PIPE_ERROR
C1-11216-1	0x80028221	SCE_KERNEL_ERROR_UNKNOWN_MSG_PIPE_ID
C1-11217-2	0x80028222	SCE_KERNEL_ERROR_MSG_PIPE_FULL
C1-11218-3	0x80028223	SCE_KERNEL_ERROR_MSG_PIPE_EMPTY
C1-11219-4	0x80028224	SCE_KERNEL_ERROR_MSG_PIPE_DELETED
C1-11220-6	0x80028240	SCE_KERNEL_ERROR_TIMER_ERROR
C1-11221-7	0x80028241	SCE_KERNEL_ERROR_UNKNOWN_TIMER_ID
C1-11222-8	0x80028242	SCE_KERNEL_ERROR_EVENT_NOT_SET
C1-11223-9	0x80028260	SCE_KERNEL_ERROR_SIMPLE_EVENT_ERROR
C1-11224-0	0x80028261	SCE_KERNEL_ERROR_UNKNOWN_SIMPLE_EVENT_ID
C1-11225-1	0x80028280	SCE_KERNEL_ERROR_PMON_ERROR
C1-11226-2	0x80028281	SCE_KERNEL_ERROR_PMON_NOT_THREAD_MODE
C1-11227-3	0x80028282	SCE_KERNEL_ERROR_PMON_NOT_CPU_MODE
NP-11288-0	0x80550718	SCE_NP_COMMUNITY_ERROR_TOO_MANY_SLOTID
NP-11289-1	0x80550719	SCE_NP_COMMUNITY_ERROR_TOO_MANY_NPID
C0-11468-0	0x8080201d	SCE_APPMGR_ERROR_TOO_LONG_ARGV
C0-11469-1	0x8080201e	SCE_APPMGR_ERROR_INVALID_SELF_PATH

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-11824-6	0x80020011	SCE_KERNEL_ERROR_ILLEGAL_OPEN_LIMIT
C1-11825-7	0x80021100	SCE_KERNEL_ERROR_PA_ERROR
C1-11826-8	0x80021101	SCE_KERNEL_ERROR_PA_NOT_AVAILABLE
C1-11827-9	0x80021102	SCE_KERNEL_ERROR_PA_INVALID_KEY
C1-11828-0	0x80024308	SCE_KERNEL_ERROR_CANNOT_GROW_PHYMEMPART
C1-11829-1	0x8002450c	SCE_KERNEL_ERROR_UID_MAX_OPEN
C1-11830-3	0x80024904	SCE_KERNEL_ERROR_HEAPLIB_VERIFY_ERROR
C1-11831-4	0x80027208	SCE_KERNEL_ERROR_CANCELING
C1-11832-5	0x80028061	SCE_KERNEL_ERROR_UNKNOWN_THREAD_EVENT_ID
C1-11833-6	0x800280a3	SCE_KERNEL_ERROR_CALLBACK_NOT_REGISTERED
C1-11834-7	0x80028168	SCE_KERNEL_ERROR_FAST_MUTEX_NOT_INITIALIZED
C1-11835-8	0x8002900b	SCE_KERNEL_ERROR_NO_PROCESS_DATA
C1-11836-9	0x8002d0f0	SCE_KERNEL_ERROR_PRELOAD_FAILED
C1-11837-0	0x8002d0f1	SCE_KERNEL_ERROR_PRELOAD_LIBC_FAILED
C1-11838-1	0x8002d0f2	SCE_KERNEL_ERROR_PRELOAD_FIOS2_FAILED
C0-11839-2	0x804a000c	SCE_NGS_ERROR_INVALID_HANDLE
C0-11840-4	0x804a000d	SCE_NGS_ERROR_SIZE_MISMATCH
C0-11841-5	0x804a000e	SCE_NGS_ERROR_PATCH_NOT_AVAILABLE
C0-11842-6	0x804a000f	SCE_NGS_ERROR_PARAM_TYPE_MISMATCH
C1-11843-7	0x8001008f	SCE_ERROR_ERRNO_EICV
C2-11892-1	0x80100660	SCE_APPUTIL_ERROR_DRM_NO_ENTITLEMENT
C2-11893-2	0x80100680	SCE_APPUTIL_ERROR_PHOTO_DEVICE_NOT_FOUND
C1-11894-3	0x80020424	SCE_COMMON_DIALOG_ERROR_WITHIN_SCENE
C1-11895-4	0x80020433	SCE_COMMON_DIALOG_ERROR_INVALID_INFOBAR_PARAM
C1-11896-5	0x80020434	SCE_COMMON_DIALOG_ERROR_INVALID_BG_COLOR
C1-11897-6	0x80020435	SCE_COMMON_DIALOG_ERROR_INVALID_DIMMER_COLOR
C2-11898-7	0x80105600	SCE_HANDWRITING_ERROR_INVALID_POINTER
C2-11899-8	0x80105601	SCE_HANDWRITING_ERROR_INVALID_PARAM
C2-11900-1	0x80105602	SCE_HANDWRITING_ERROR_NOT_OPENED
C2-11901-2	0x80105603	SCE_HANDWRITING_ERROR_ALREADY_INITIALIZED
C2-11902-3	0x80105604	SCE_HANDWRITING_ERROR_NOT_INITIALIZED
C2-11903-4	0x80105605	SCE_HANDWRITING_ERROR_READ
C2-11904-5	0x80105606	SCE_HANDWRITING_ERROR_MEMORY_ERROR
C2-11905-6	0x80105607	SCE_HANDWRITING_ERROR_DIC_FULL
C2-11906-7	0x80105610	SCE_HANDWRITING_ERROR_INTERNAL
NW-11907-8	0x80412116	SCE_NET_CTL_ERROR_WIFI_DEAUTHED
NW-11908-9	0x80412117	SCE_NET_CTL_ERROR_WIFI_BEACON_LOST
NW-11909-0	0x80412118	SCE_NET_CTL_ERROR_DISCONNECTED_FOR_SUSPEND
C2-11910-2	0x8010491f	SCE_NEAR_ERROR_DB_LOCKED
C2-11911-3	0x80104920	SCE_NEAR_ERROR_INVALID_VERSION
C2-11912-4	0x80104921	SCE_NEAR_ERROR_NETWORK_TIME_NOT_INITIALIZED
C2-11914-6	0x80104923	SCE_NEAR_ERROR_INVALID_IMAGE
C2-11915-7	0x80100c05	SCE_NETCHECK_DIALOG_ERROR_LATEST_PATCH_PKG_EXIST
NP-11916-8	0x80551d0c	SCE_NP_BASIC_ERROR_IPC_QUEUE_OVERFLOWED
C2-11917-9	0x80100f04	SCE_NP_PROFILE_DIALOG_ERROR_LACK_OF_LIBHTTP_POOL_SIZE
C2-11918-0	0x80100f05	SCE_NP_PROFILE_DIALOG_ERROR_LACK_OF_LIBSSL_POOL_SIZE
C2-11919-1	0x80103708	SCE_PHOTOVIEW_DIALOG_ERROR_REQUIRED_PRX_IS_NOT_LOADED
C2-11920-3	0x80101a0f	SCE_PHOTO_EXPORT_ERROR_INVALID_PATH
C2-11921-4	0x80105201	SCE_SHUTTER_SOUND_ERROR_INVALID_ARGUMENT
C2-11922-5	0x80105202	SCE_SHUTTER_SOUND_ERROR_INTERNAL
C2-11923-6	0x80105203	SCE_SHUTTER_SOUND_ERROR_FATAL
C2-11924-7	0x80105301	SCE_MUSIC_EXPORT_ERROR_PARAM
C2-11925-8	0x80105302	SCE_MUSIC_EXPORT_ERROR_FILE_NOT_FOUND
C2-11926-9	0x80105303	SCE_MUSIC_EXPORT_ERROR_CONTENT_FULL

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-11927-0	0x80105304	SCE MUSIC_EXPORT_ERROR_NO_MEMORY
C2-11928-1	0x80105305	SCE MUSIC_EXPORT_ERROR_SERVER_DOWN
C2-11929-2	0x80105306	SCE MUSIC_EXPORT_ERROR_TOO_MANY_CLIENT
C2-11930-4	0x80105307	SCE MUSIC_EXPORT_ERROR_MEDIA_FULL
C2-11931-5	0x80105308	SCE MUSIC_EXPORT_ERROR_CREATE_FILE
C2-11932-6	0x80105309	SCE MUSIC_EXPORT_ERROR_NOT_SUPPORTED_FORMAT
C2-11933-7	0x8010530a	SCE MUSIC_EXPORT_ERROR_CANCELED
C2-11934-8	0x8010530b	SCE MUSIC_EXPORT_ERROR_INTERNAL
C2-11935-9	0x8010530c	SCE MUSIC_EXPORT_ERROR_MEDIA_NOT_EXIST
C2-11936-0	0x8010530d	SCE MUSIC_EXPORT_ERROR_DB_CORRUPTED
C2-11937-1	0x8010530e	SCE MUSIC_EXPORT_ERROR_INVALID_PATH
C0-12078-8	0x805b0019	SCE GXM_ERROR_INVALID_TEXTURE_DATA_POINTER
C0-12079-9	0x805b001a	SCE GXM_ERROR_INVALID_TEXTURE_PALETTE_POINTER
C0-12080-1	0x805b001b	SCE GXM_ERROR_INVALID_OUTPUT_REGISTER_SIZE
C0-12081-2	0x805b001c	SCE GXM_ERROR_INVALID_FRAGMENT_MSAA_MODE
C0-12082-3	0x805b001d	SCE GXM_ERROR_INVALID_VISIBILITY_BUFFER_POINTER
C0-12083-4	0x805b001e	SCE GXM_ERROR_INVALID_VISIBILITY_INDEX
C0-12084-5	0x805b001f	SCE GXM_ERROR_INVALID_DEPTH_STENCIL_CONFIGURATION
C0-12085-6	0x805b0020	SCE GXM_ERROR_INVALID_TEXTURE
C0-12086-7	0x805b0021	SCE GXM_ERROR_OUT_OF_HOST_MEMORY
C0-12087-8	0x805b0022	SCE GXM_ERROR_OUT_OF_BUFFER_MEMORY
C0-12088-9	0x805b0023	SCE GXM_ERROR_OUT_OF_VERTEX_USSE_MEMORY
C0-12089-0	0x805b0024	SCE GXM_ERROR_OUT_OF_FRAGMENT_USSE_MEMORY
C0-12090-2	0x805b0025	SCE GXM_ERROR_INVALID_PRIMITIVE_TYPE
C1-12389-3	0x80021103	SCE KERNEL_ERROR_PA_KEY_IS_NOT_SHARED
C1-12390-5	0x80021104	SCE KERNEL_ERROR_PA_INVALID_SIGNATURE
C1-12391-6	0x8002450d	SCE KERNEL_ERROR_UID_RL_OVERFLOW
C1-12392-7	0x80024b09	SCE KERNEL_ERROR_MEMBLOCK_RANGE_ERROR
C1-12393-8	0x80028300	SCE KERNEL_ERROR_WORK_QUEUE
C1-12394-9	0x80028301	SCE KERNEL_ERROR_UNKNOWN_WORK_QUEUE_ID
C1-12395-0	0x80028302	SCE KERNEL_ERROR_UNKNOWN_WORK_TASK_ID
C1-12396-1	0x8002900c	SCE KERNEL_ERROR_PROCESS_EVENT_INHIBITED
C2-12401-8	0x80105608	SCE HANDWRITING_ERROR_CODE_ERROR
C2-12402-9	0x80101240	SCE LOCATION_ERROR_INVALID_ADDRESS
C2-12403-0	0x80101241	SCE LOCATION_ERROR_INVALID_HANDLE
C2-12404-1	0x80101242	SCE LOCATION_ERROR_NO_MEMORY
C2-12405-2	0x80101243	SCE LOCATION_ERROR_TOO_MANY_HANDLES
C2-12406-3	0x80101244	SCE LOCATION_ERROR_INVALID_LOCATION_METHOD
C2-12407-4	0x80101245	SCE LOCATION_ERROR_INVALID_HEADING_METHOD
C2-12408-5	0x80101246	SCE LOCATION_ERROR_MULTIPLE_CALLBACK
C2-12409-6	0x80101247	SCE LOCATION_ERROR_NOT_RUNNING_CALLBACK
C2-12410-8	0x80101248	SCE LOCATION_ERROR_DIALOG_RESULT_NONE
C2-12411-9	0x80101249	SCE LOCATION_ERROR_DISABLE_APPLICATION
C2-12412-0	0x8010124a	SCE LOCATION_ERROR_MULTIPLE_CONFIRM
C2-12413-1	0x8010124b	SCE LOCATION_ERROR_DISABLE_DEBUG_API
C2-12414-2	0x8010124c	SCE LOCATION_ERROR_INVALID_TIMING
C2-12415-3	0x8010124d	SCE LOCATION_ERROR_INVALID_VALUE
C2-12416-4	0x8010124e	SCE LOCATION_ERROR_INITIALIZED
C2-12417-5	0x8010124f	SCE LOCATION_ERROR_UNINITIALIZED
C2-12418-6	0x80101280	SCE LOCATION_ERROR_UNAUTHORIZED
C2-12419-7	0x80101281	SCE LOCATION_ERROR_PROVIDER_UNAVAILABLE
C2-12420-9	0x80101282	SCE LOCATION_ERROR_FILE_IO
C2-12421-0	0x80101283	SCE LOCATION_ERROR_INVALID_FILE_FORMAT
C2-12422-1	0x80101284	SCE LOCATION_ERROR_TIME_OUT
C2-12423-2	0x80101285	SCE LOCATION_ERROR_NO_SERVER_MEMORY
C2-12424-3	0x80101286	SCE LOCATION_ERROR_INVALID_TITLE_ID
C2-12425-4	0x80101287	SCE LOCATION_ERROR_INTERNAL_FILE_INVALID

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-12426-5	0x8010128f	SCE_LOCATION_ERROR_CANNOT_CHANGE_ALLOCATOR
C2-12427-6	0x801012ff	SCE_LOCATION_ERROR_FATAL_ERROR
C2-12428-7	0x801012e0	SCE_LOCATION_DBGERROR_EMULATION_FILE_ERROR
NW-12436-6	0x80412119	SCE_NET_CTL_ERROR_COMMUNICATION_ID_NOT_EXIST
NP-12438-8	0x80552306	SCE_NP_ACTIVITY_ERROR_SIGNOUT
NP-12439-9	0x80552307	SCE_NP_ACTIVITY_ERROR_INTERNAL
NP-12440-1	0x80552507	SCE_NP_PARTY_ERROR_VOICE_NOT_ENABLED
NP-12441-2	0x80552508	SCE_NP_PARTY_ERROR_PARTY_MEMBER_NOT_FOUND
NP-12548-0	0x80551e08	SCE_NP_MESSAGE_ERROR_INVALID_NPCOMMID
C0-12561-5	0x805b0026	SCE_GXM_ERROR_INVALID_MAPPING
C0-12721-3	0x80600002	SCE_CODECEENGINE_ERROR_INVALID_ALIGNMENT
C0-12722-4	0x80600003	SCE_CODECEENGINE_ERROR_NOT_PHYSICALLY_CONTIGUOUS
C0-12723-5	0x80600004	SCE_CODECEENGINE_ERROR_INVALID_RANGE
C0-12724-6	0x80600005	SCE_CODECEENGINE_ERROR_INVALID_HEAP
C0-12725-7	0x80600006	SCE_CODECEENGINE_ERROR_HEAP_BROKEN
C0-12726-8	0x80600007	SCE_CODECEENGINE_ERROR_NO_MORE_ENTRY
C0-12727-9	0x80600008	SCE_CODECEENGINE_ERROR_INVALID_MEMTYPE
C0-12728-0	0x80600009	SCE_CODECEENGINE_ERROR_INVALID_VALUE
C0-12729-1	0x8060000a	SCE_CODECEENGINE_ERROR_MEMORY_NOT_ALLOCATED
C0-12730-3	0x8060000b	SCE_CODECEENGINE_ERROR_MEMORY_IN_USE
C0-12731-4	0x8060000c	SCE_CODECEENGINE_ERROR_MEMORY_NOT_IN_USE
C1-12732-5	0x80024309	SCE_KERNEL_ERROR_NO_FREE_PHYSICAL_PAGE_CDRAM
C1-12733-6	0x80024b0a	SCE_KERNEL_ERROR_MEMBLOCK_TYPE_FOR_UPDATER_OR_SAFEMODE
NW-12762-8	0x8041211a	SCE_NET_CTL_ERROR_ADHOC_ALREADY_CONNECTED
C2-12763-9	0x80100c06	SCE_NETCHECK_DIALOG_ERROR_SIGN_OUT
NP-12764-0	0x8055082d	SCE_NP_COMMUNITY_SERVER_ERROR_TOO_MANY_RESULTS
NP-12765-1	0x8055082e	SCE_NP_COMMUNITY_SERVER_ERROR_NOT_RECORDABLE_VERSION
NP-12766-2	0x80550848	SCE_NP_COMMUNITY_SERVER_ERROR_USER_STORAGE_TITLE_MASTER_NOT_FOUND
NP-12767-3	0x80550849	SCE_NP_COMMUNITY_SERVER_ERROR_INVALID_VIRTUAL_USER
NP-12768-4	0x8055084a	SCE_NP_COMMUNITY_SERVER_ERROR_USER_STORAGE_DATA_NOT_FOUND
NP-12769-5	0x80550857	SCE_NP_COMMUNITY_SERVER_ERROR_INVALID_AVATAR_PAP
NP-12770-7	0x8055085d	SCE_NP_COMMUNITY_SERVER_ERROR_NON_PLUS_MEMBER
NP-12771-8	0x8055085e	SCE_NP_COMMUNITY_SERVER_ERROR_UNMATCH_SEQUENCE
NP-12772-9	0x8055085f	SCE_NP_COMMUNITY_SERVER_ERROR_SAVEDATA_NOT_FOUND
NP-12773-0	0x80550860	SCE_NP_COMMUNITY_SERVER_ERROR_TOO_MANY_SAVEDATA_FILES
NP-12774-1	0x80550861	SCE_NP_COMMUNITY_SERVER_ERROR_TOO_MUCH_TOTAL_SAVEDATA_SIZE
NP-12775-2	0x80550862	SCE_NP_COMMUNITY_SERVER_ERROR_NOT_YET_DOWNLOADABLE
NP-12776-3	0x80550868	SCE_NP_COMMUNITY_SERVER_ERROR_BLACKLISTED_TITLE
NP-12777-4	0x80550869	SCE_NP_COMMUNITY_SERVER_ERROR_TOO_LARGE_ICONDATA
NP-12778-5	0x8055086e	SCE_NP_COMMUNITY_SERVER_ERROR_RECORD_DATE_IS_NEWER_THAN_COMP_DATE
NP-12779-6	0x8055086a	SCE_NP_COMMUNITY_SERVER_ERROR_TOO_LARGE_SAVEDATA
NP-12780-8	0x8055086b	SCE_NP_COMMUNITY_SERVER_ERROR_UNMATCH_SIGNATURE
NP-12781-9	0x8055086c	SCE_NP_COMMUNITY_SERVER_ERROR_UNMATCH_MD5SUM
NP-12782-0	0x8055086d	SCE_NP_COMMUNITY_SERVER_ERROR_TOO_MUCH_SAVEDATA_SIZE
NP-12783-1	0x80550873	SCE_NP_COMMUNITY_SERVER_ERROR_CONDITIONS_NOT_SATISFIED
NP-12784-2	0x80550878	SCE_NP_COMMUNITY_SERVER_ERROR_UNSUPPORTED_PLATFORM
C0-12841-6	0x805b0027	SCE_GXM_ERROR_OUT_OF_RENDER_TARGETS
C0-12842-7	0x805b0028	SCE_GXM_ERROR_INVALID_VISIBILITY_OP

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-12889-8	0x80024b0b	SCE_KERNEL_ERROR_MEMBLOCK_OVERFLOW
C0-12894-4	0x80820021	SCE_FIOS_ERROR_BAD_FLAGS SCE_FIOS_KERNEL_ERROR_BAD_FLAGS
C0-13002-6	0x80620041	SCE_AVCDEC_ERROR_INVALID_PICTURE
C0-13035-2	0x80620840	SCE_VIDEDEC_ERROR_NOT_GAME_BUDGET
C0-13082-4	0x80630001	SCE_ATRAC_ERROR_INVALID_SIZE
C0-13083-5	0x80630002	SCE_ATRAC_ERROR_INVALID_WORD_LENGTH
C0-13084-6	0x80630003	SCE_ATRAC_ERROR_INVALID_TYPE
C0-13085-7	0x80630004	SCE_ATRAC_ERROR_INVALID_TOTAL_CH
C0-13086-8	0x80630005	SCE_ATRAC_ERROR_INVALID_ALIGNMENT
C0-13087-9	0x80630006	SCE_ATRAC_ERROR_ALREADY_CREATED
C0-13088-0	0x80630007	SCE_ATRAC_ERROR_NOT_CREATED
C0-13089-1	0x80630008	SCE_ATRAC_ERROR_SHORTAGE_OF_CH
C0-13090-3	0x80630009	SCE_ATRAC_ERROR_UNSUPPORTED_DATA
C0-13091-4	0x8063000a	SCE_ATRAC_ERROR_INVALID_DATA
C0-13092-5	0x8063000b	SCE_ATRAC_ERROR_READ_SIZE_IS_TOO_SMALL
C0-13093-6	0x8063000c	SCE_ATRAC_ERROR_INVALID_HANDLE
C0-13094-7	0x8063000d	SCE_ATRAC_ERROR_READ_SIZE_OVER_BUFFER
C0-13095-8	0x8063000e	SCE_ATRAC_ERROR_MAIN_BUFFER_SIZE_IS_TOO_SMALL
C0-13096-9	0x8063000f	SCE_ATRAC_ERROR_SUB_BUFFER_SIZE_IS_TOO_SMALL
C0-13097-0	0x80630010	SCE_ATRAC_ERROR_DATA_SHORTAGE_IN_BUFFER
C0-13098-1	0x80630011	SCE_ATRAC_ERROR_ALL_DATA_WAS_DECODED
C0-13099-2	0x80630012	SCE_ATRAC_ERROR_INVALID_MAX_OUTPUT_SAMPLES
C0-13100-5	0x80630013	SCE_ATRAC_ERROR_ADDED_DATA_IS_TOO_BIG
C0-13101-6	0x80630014	SCE_ATRAC_ERROR_NEED_SUB_BUFFER
C0-13102-7	0x80630015	SCE_ATRAC_ERROR_INVALID_SAMPLE
C0-13103-8	0x80630016	SCE_ATRAC_ERROR_NO_NEED_SUB_BUFFER
C0-13104-9	0x80630017	SCE_ATRAC_ERROR_INVALID_LOOP_STATUS
C0-13105-0	0x80630018	SCE_ATRAC_ERROR_REMAIN_VALID_HANDLE
C0-13106-1	0x80630030	SCE_ATRAC_ERROR_INVALID_LOOP_NUM
C0-13107-2	0x807f000f	SCE_AUDIODEC_ERROR_INVALID_NFRAMES
C0-13108-3	0x807f0010	SCE_AUDIODEC_ERROR_INVALID_NSTREAMS
C0-13109-4	0x807f0011	SCE_AUDIODEC_ERROR_DIFFERENT_TYPES
C0-13110-6	0x807f0012	SCE_AUDIODEC_ERROR_SAME_HANDLES
C1-13111-7	0x80020012	SCE_KERNEL_ERROR_ONLY_DEVELOPMENT_MODE
C1-13112-8	0x8002430a	SCE_KERNEL_ERROR_INVALID_SUBBUDGET_ID
C0-13113-9	0x804a0010	SCE_NGS_ERROR_INVALID_STATE
C1-13114-0	0x8008c008	SCE_RAZOR_GPU_ERROR_SETTINGS_NOT_FOUND
C1-13122-9	0x80020408	SCE_COMMON_DIALOG_ERROR_NOT_AVAILABLE
C2-13128-5	0x80106301	SCE_NOTIFICATION_ERROR_PARAM
C2-13129-6	0x801063ff	SCE_NOTIFICATION_ERROR_INTERNAL
C2-13130-8	0x8010400b	SCE_LIVEAREA_ERROR_DIRPATH
NP-13131-9	0x80551d0e	SCE_NP_BASIC_ERROR_NO_NP_COMM_ID_IN_PARAM_SFO
NP-13132-0	0x80550d33	SCE_NP_MATCHING2_SERVER_ERROR_BLOCKED_USER_IN_ROOM
NP-13133-1	0x80551e09	SCE_NP_MESSAGE_ERROR_SESSION_INVALID
NP-13134-2	0x80551e0a	SCE_NP_MESSAGE_FATAL_DB_ERROR
NP-13135-3	0x80552601	SCE_NP_SNS_FACEBOOK_ERROR_UNKNOWN
NP-13136-4	0x80552602	SCE_NP_SNS_FACEBOOK_ERROR_ALREADY_INITIALIZED
NP-13137-5	0x80552603	SCE_NP_SNS_FACEBOOK_ERROR_NOT_INITIALIZED
NP-13138-6	0x80552604	SCE_NP_SNS_FACEBOOK_ERROR_INVALID_ARGUMENT
NP-13139-7	0x80552605	SCE_NP_SNS_FACEBOOK_ERROR_OUT_OF_MEMORY
NP-13140-9	0x80552606	SCE_NP_SNS_FACEBOOK_ERROR_EXCEEDS_MAX
NP-13141-0	0x80552607	SCE_NP_SNS_FACEBOOK_ERROR_NOT_SIGNIN
NP-13142-1	0x80552608	SCE_NP_SNS_FACEBOOK_ERROR_CHAT_RESTRICTION
NP-13143-2	0x80552609	SCE_NP_SNS_FACEBOOK_ERROR_ABORTED
NP-13144-3	0x8055260a	SCE_NP_SNS_FACEBOOK_ERROR_FACEBOOK_SERVER_ERROR
NP-13145-4	0x8055260b	SCE_NP_SNS_FACEBOOK_ERROR_ACCESS_NOT_ALLOWED

©SCEI



SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-13146-5	0x8055260c	SCE NP SNS FACEBOOK ERROR AUTH ERROR
NP-13147-6	0x8055260d	SCE NP SNS FACEBOOK ERROR ACCOUNT NOT BOUND
NP-13148-7	0x8055260e	SCE NP SNS FACEBOOK ERROR CONFIG DISABLED
NP-13149-8	0x8055260f	SCE NP SNS FACEBOOK ERROR CANCELED BY SYSTEM
C2-13150-0	0x80106101	SCE NP SNS FACEBOOK DIALOG ERROR INTERNAL
C2-13151-1	0x80106102	SCE NP SNS FACEBOOK DIALOG ERROR REQUIRED_MODULES_NOT_LOADED
C2-13152-2	0x80106103	SCE NP SNS FACEBOOK DIALOG ERROR PARAM
C2-13153-3	0x80106104	SCE NP SNS FACEBOOK DIALOG ERROR NOT SIGNIN
C2-13154-4	0x80106105	SCE NP SNS FACEBOOK DIALOG ERROR CHAT RESTRICTION
NW-13155-5	0x80770001	SCE RUDP ERROR NOT INITIALIZED
NW-13156-6	0x80770002	SCE RUDP ERROR ALREADY INITIALIZED
NW-13157-7	0x80770003	SCE RUDP ERROR INVALID CONTEXT ID
NW-13158-8	0x80770004	SCE RUDP ERROR INVALID ARGUMENT
NW-13159-9	0x80770005	SCE RUDP ERROR INVALID OPTION
NW-13160-1	0x80770006	SCE RUDP ERROR INVALID MUXMODE
NW-13161-2	0x80770007	SCE RUDP ERROR MEMORY
NW-13162-3	0x80770008	SCE RUDP ERROR INTERNAL
NW-13163-4	0x80770009	SCE RUDP ERROR CONN RESET
NW-13164-5	0x8077000a	SCE RUDP ERROR CONN REFUSED
NW-13165-6	0x8077000b	SCE RUDP ERROR CONN TIMEOUT
NW-13166-7	0x8077000c	SCE RUDP ERROR CONN VERSION MISMATCH
NW-13167-8	0x8077000d	SCE RUDP ERROR CONN TRANSPORT TYPE MISMATCH
NW-13168-9	0x8077000e	SCE RUDP ERROR CONN QUALITY LEVEL MISMATCH
NW-13169-0	0x8077000f	SCE RUDP ERROR THREAD
NW-13170-2	0x80770010	SCE RUDP ERROR THREAD IN USE
NW-13171-3	0x80770011	SCE RUDP ERROR NOT ACCEPTABLE
NW-13172-4	0x80770012	SCE RUDP ERROR MSG TOO LARGE
NW-13173-5	0x80770013	SCE RUDP ERROR NOT BOUND
NW-13174-6	0x80770014	SCE RUDP ERROR CANCELLED
NW-13175-7	0x80770015	SCE RUDP ERROR INVALID VPORT
NW-13176-8	0x80770016	SCE RUDP ERROR WOULDLOCK
NW-13177-9	0x80770017	SCE RUDP ERROR VPORT IN USE
NW-13178-0	0x80770018	SCE RUDP ERROR VPORT EXHAUSTED
NW-13179-1	0x80770019	SCE RUDP ERROR INVALID SOCKET
NW-13180-3	0x8077001a	SCE RUDP ERROR BUFFER TOO SMALL
NW-13181-4	0x8077001b	SCE RUDP ERROR MSG MALFORMED
NW-13182-5	0x8077001c	SCE RUDP ERROR ADDR IN USE
NW-13183-6	0x8077001d	SCE RUDP ERROR ALREADY BOUND
NW-13184-7	0x8077001e	SCE RUDP ERROR ALREADY EXISTS
NW-13185-8	0x8077001f	SCE RUDP ERROR INVALID POLL ID
NW-13186-9	0x80770020	SCE RUDP ERROR TOO MANY CONTEXTS
NW-13187-0	0x80770021	SCE RUDP ERROR IN PROGRESS
NW-13188-1	0x80770022	SCE RUDP ERROR NO EVENT HANDLER
NW-13189-2	0x80770023	SCE RUDP ERROR PAYLOAD TOO LARGE
NW-13190-4	0x80770024	SCE RUDP ERROR END OF DATA
NW-13191-5	0x80770025	SCE RUDP ERROR ALREADY ESTABLISHED
NW-13192-6	0x80770026	SCE RUDP ERROR KEEP ALIVE FAILURE
C2-13327-6	0x80104924	SCE NEAR ERROR TIME RETRIEVE FAILED
NW-13347-8	0x8041211b	SCE NET CTL ERROR DHCP TIMEOUT
NW-13348-9	0x8041211c	SCE NET CTL ERROR PPPOE TIMEOUT
C1-13457-0	0x800281c3	SCE KERNEL ERROR WAIT DELETE LW COND
C2-13458-1	0x80106106	SCE NP SNS FACEBOOK DIALOG ERROR_LIBRARY_NOT_INITIALIZED
C0-13532-4	0x80580002	SCE PERF ERROR BAD TRACE DATA
NP-13560-5	0x80551e0b	SCE NP MESSAGE ERROR INTERNAL IMAP
NP-13561-6	0x80551e0d	SCE NP MESSAGE ERROR INTERNAL CACHE

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NP-13562-7	0x80551e0e	SCE NP MESSAGE ERROR INTERNAL MIME
NP-13596-4	0x80551e0c	SCE NP MESSAGE ERROR NOT SIGNIN
NP-13616-7	0x8055071a	SCE NP COMMUNITY ERROR SCORE INVALID SAVEDATA OWNER
NP-13617-8	0x8055071b	SCE NP COMMUNITY ERROR TUS INVALID SAVEDATA OWNER
C2-13618-9	0x80102204	SCE_STORE_CHECKOUT_DIALOG_ERROR_ADDCONT_BUSY
C1-13675-2	0x80028320	SCE_KERNEL_ERROR_EXCEPTION
C1-13676-3	0x80028321	SCE_KERNEL_ERROR_EXCEPTION_MULTI
C2-13677-4	0x80100685	SCE_APPUTIL_ERROR_MUSIC_DEVICE_NOT_FOUND
C2-13678-5	0x80101250	SCE_LOCATION_ERROR_MULTIPLE_GET_LOCATION
C2-13936-2	0x80102f0b	SCE_SCREENSHOT_ERROR_MEDIA_NOT_EXIST
C2-13937-3	0x80102f0c	SCE_SCREENSHOT_ERROR_CONTENT_FULL
C2-13938-4	0x80102f08	SCE_SCREENSHOT_ERROR_CAPTURE_FAILED
C0-14013-9	0x8086000f	SCE_AUDIOENC_ERROR_UNSUPPORTED
C4-14015-1	0x8026010b	SCE_AUDIO_IN_ERROR_INVALID_PARAMETER
C1-14016-2	0x800a0001	SCE_COREDUMP_ERROR_NOT_REGISTERED
C1-14017-3	0x800a0002	SCE_COREDUMP_ERROR_ALREADY_REGISTERED
C1-14018-4	0x800a0003	SCE_COREDUMP_ERROR_NOT_IN_COREDUMP_HANDLER
C1-14019-5	0x8002200a	SCE_KERNEL_ERROR_NOT_L2PTE
C1-14020-7	0x80024004	SCE_KERNEL_ERROR_NOT_PA_ADDRESS
C1-14021-8	0x8002450e	SCE_KERNEL_ERROR_UID_FOR_PRODCESS_OVERFLOW
C1-14022-9	0x80024a04	SCE_KERNEL_ERROR_ADDRESS_SPACE_CANNOT_FIND_L2PAGETA BLE
C1-14023-0	0x80024b0c	SCE_KERNEL_ERROR_ILLEGAL_MEMBLOCK_PERMISSION
C1-14024-1	0x80024b0d	SCE_KERNEL_ERROR_MEMBLOCK_NOT_ALLOW_REMAP_OP
C1-14025-2	0x80024b0e	SCE_KERNEL_ERROR_ADDRESS_SPACE_LOCK_ERROR
C1-14026-3	0x80024b0f	SCE_KERNEL_ERROR_ADDRESS_SPACE_UNLOCK_ERROR
NW-14027-4	0x80435200	SCE_SSL_ERROR_R_ERROR_BASE
NW-14028-5	0x80435201	SCE_SSL_ERROR_R_ERROR_FAILED
NW-14029-6	0x804352ff	SCE_SSL_ERROR_R_ERROR_UNKNOWN
C0-14030-8	0x804a0011	SCE_NGS_ERROR_INTERNAL_ALLOC
C0-14031-9	0x804a0012	SCE_NGS_ERROR_INTERNAL_PROCESSING
C0-14032-0	0x804a0013	SCE_NGS_ERROR_INVALID_BUFFER
C2-14071-3	0x80107401	SCE_CROSS_CONTROLLER_DIALOG_ERROR_PARAM
C2-14072-4	0x80107402	SCE_CROSS_CONTROLLER_DIALOG_ERROR_INTERNAL
C2-14073-5	0x80107403	SCE_CROSS_CONTROLLER_DIALOG_ERROR_MISMATCH_APP
C2-14074-6	0x80107404	SCE_CROSS_CONTROLLER_DIALOG_ERROR_NEED_UPDATE_VITA_ SYS
C2-14075-7	0x80107405	SCE_CROSS_CONTROLLER_DIALOG_ERROR_NEED_UPDATE_VITA_ APP
C2-14076-8	0x80107406	SCE_CROSS_CONTROLLER_DIALOG_ERROR_NEED_UPDATE_PS3_S YS
C2-14077-9	0x80107407	SCE_CROSS_CONTROLLER_DIALOG_ERROR_NEED_UPDATE_PS3_A PP
C2-14078-0	0x80107701	SCE_DTCP_IP_ERROR_CANCEL
C2-14079-1	0x80107702	SCE_DTCP_IP_ERROR_GENERIC
C2-14080-3	0x80107703	SCE_DTCP_IP_ERROR_SEQUENCE
C2-14081-4	0x80107704	SCE_DTCP_IP_ERROR_PARAM
C2-14082-5	0x80107705	SCE_DTCP_IP_ERROR_AUTH_INVALID_HOSTNAME
C2-14083-6	0x80107706	SCE_DTCP_IP_ERROR_AUTH_SERVER_NOT_FOUND
C2-14084-7	0x80107707	SCE_DTCP_IP_ERROR_AUTH_CANNOT_ACCESS
C2-14085-8	0x80107708	SCE_DTCP_IP_ERROR_AUTH_FAILED
C2-14086-9	0x80107709	SCE_DTCP_IP_ERROR_AUTH_FAILED_WLAN
C2-14087-0	0x8010770a	SCE_DTCP_IP_ERROR_DEVCERT_EXPIRED
C2-14088-1	0x8010770b	SCE_DTCP_IP_ERROR_KEY_NEED_ACTIVATE
C2-14089-2	0x8010770c	SCE_DTCP_IP_ERROR_KEY_NEED_UPDATE
C2-14090-4	0x8010770d	SCE_DTCP_IP_ERROR_KEY_FATAL
C2-14091-5	0x8010770e	SCE_DTCP_IP_ERROR_KEY_NEED_CLOCK_SETUP

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-14092-6	0x8010770f	SCE DTCP IP ERROR STREAM GENERIC
C2-14093-7	0x80107710	SCE DTCP IP ERROR HTTP CONNECTION CLOSED
C2-14094-8	0x80107711	SCE DTCP IP ERROR ACTIVATE GENERIC
C2-14095-9	0x80107712	SCE DTCP IP ERROR ACTIVATE INTERNAL
C2-14096-0	0x80107713	SCE DTCP IP ERROR MOVE COMMITMENT ABORTED
C2-14097-1	0x80107714	SCE DTCP IP ERROR MOVE COMMITMENT NEED RETRY
C2-14098-2	0x80107715	SCE DTCP IP ERROR OUT OF MEMORY
C2-14099-3	0x8010071c	SCE IME ERROR INVALID ENTER LABEL
NW-14100-6	0x8041211d	SCE NET CTL ERROR INSUFFICIENT MEMORY
C2-14103-9	0x80100a02	SCE MSG DIALOG ERROR MODULE
C2-14104-0	0x80100c07	SCE NETCHECK DIALOG ERROR INVALID PSPADHOC PARAM
NP-14105-1	0x80551d0f	SCE NP BASIC ERROR JOIN GAME ACK REQUEST TIMEDOUT
NP-14106-2	0x80551d10	SCE NP BASIC ERROR JOIN GAME ACK REQUEST CANCELED
NP-14107-3	0x80551d11	SCE NP BASIC ERROR JOIN GAME ACK REQUEST INVALID
NP-14108-4	0x805508b0	SCE NP COMMUNITY SERVER ERROR UBS BEFORE SERVICE
NP-14109-5	0x80551f05	SCE NP BANDWIDTH TEST ERROR INVALID ARGUMENT
NP-14110-7	0x80552701	SCE NP SIGNALING ERROR NOT INITIALIZED
NP-14111-8	0x80552702	SCE NP SIGNALING ERROR ALREADY INITIALIZED
NP-14112-9	0x80552703	SCE NP SIGNALING ERROR OUT OF MEMORY
NP-14113-0	0x80552704	SCE NP SIGNALING ERROR CTXID NOT AVAILABLE
NP-14114-1	0x80552705	SCE NP SIGNALING ERROR CTX NOT FOUND
NP-14115-2	0x80552706	SCE NP SIGNALING ERROR REQID NOT AVAILABLE
NP-14116-3	0x80552707	SCE NP SIGNALING ERROR REQ NOT FOUND
NP-14117-4	0x80552708	SCE NP SIGNALING ERROR PARSER CREATE FAILED
NP-14118-5	0x80552709	SCE NP SIGNALING ERROR PARSER FAILED
NP-14119-6	0x8055270a	SCE NP SIGNALING ERROR INVALID NAMESPACE
NP-14120-8	0x8055270b	SCE NP SIGNALING ERROR NETINFO NOT AVAILABLE
NP-14121-9	0x8055270c	SCE NP SIGNALING ERROR PEER NOT RESPONDING
NP-14122-0	0x8055270d	SCE NP SIGNALING ERROR CONNID NOT AVAILABLE
NP-14123-1	0x8055270e	SCE NP SIGNALING ERROR CONN NOT FOUND
NP-14124-2	0x8055270f	SCE NP SIGNALING ERROR PEER UNREACHABLE
NP-14125-3	0x80552710	SCE NP SIGNALING ERROR TERMINATED BY PEER
NP-14126-4	0x80552711	SCE NP SIGNALING ERROR TIMEOUT
NP-14127-5	0x80552712	SCE NP SIGNALING ERROR CTX MAX
NP-14128-6	0x80552713	SCE NP SIGNALING ERROR RESULT NOT FOUND
NP-14129-7	0x80552714	SCE NP SIGNALING ERROR CONN IN PROGRESS
NP-14130-9	0x80552715	SCE NP SIGNALING ERROR INVALID ARGUMENT
NP-14131-0	0x80552716	SCE NP SIGNALING ERROR OWN NP ID
NP-14132-1	0x80552717	SCE NP SIGNALING ERROR TOO MANY CONN
NP-14133-2	0x80552718	SCE NP SIGNALING ERROR TERMINATED BY MYSELF
NW-14135-4	0x80410701	SCE ERROR NET ADHOC INVALID SOCKET ID
NW-14136-5	0x80410702	SCE ERROR NET ADHOC INVALID ADDR
NW-14137-6	0x80410703	SCE ERROR NET ADHOC INVALID PORT
NW-14138-7	0x80410704	SCE ERROR NET ADHOC INVALID BUFLen
NW-14139-8	0x80410705	SCE ERROR NET ADHOC INVALID DATALEN
NW-14140-0	0x80410706	SCE ERROR NET ADHOC NOT ENOUGH SPACE
NW-14141-1	0x80410707	SCE ERROR NET ADHOC SOCKET DELETED
NW-14142-2	0x80410708	SCE ERROR NET ADHOC SOCKET ALERTED
NW-14143-3	0x80410709	SCE ERROR NET ADHOC WOULD BLOCK
NW-14144-4	0x8041070a	SCE ERROR NET ADHOC PORT IN USE
NW-14145-5	0x8041070b	SCE ERROR NET ADHOC NOT CONNECTED
NW-14146-6	0x8041070c	SCE ERROR NET ADHOC DISCONNECTED
NW-14147-7	0x8041070d	SCE ERROR NET ADHOC NOT OPENED
NW-14148-8	0x8041070e	SCE ERROR NET ADHOC NOT LISTENED
NW-14149-9	0x8041070f	SCE ERROR NET ADHOC SOCKET ID NOT AVAIL
NW-14150-1	0x80410710	SCE ERROR NET ADHOC PORT NOT AVAIL
NW-14151-2	0x80410711	SCE ERROR NET ADHOC INVALID ARG

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
NW-14152-3	0x80410712	SCE_ERROR_NET_ADHOC_NOT_INITIALIZED
NW-14153-4	0x80410713	SCE_ERROR_NET_ADHOC_ALREADY_INITIALIZED
NW-14154-5	0x80410714	SCE_ERROR_NET_ADHOC_BUSY
NW-14155-6	0x80410715	SCE_ERROR_NET_ADHOC_TIMEOUT
NW-14156-7	0x80410716	SCE_ERROR_NET_ADHOC_NO_ENTRY
NW-14157-8	0x80410717	SCE_ERROR_NET_ADHOC_EXCEPTION_EVENT
NW-14158-9	0x80410718	SCE_ERROR_NET_ADHOC_CONNECTION_REFUSED
NW-14159-0	0x80410719	SCE_ERROR_NET_ADHOC_THREAD_ABORTED
NW-14160-2	0x8041071a	SCE_ERROR_NET_ADHOC_ALREADY_CREATED
NW-14161-3	0x8041071b	SCE_ERROR_NET_ADHOC_NOT_IN_GAMEMODE
NW-14162-4	0x8041071c	SCE_ERROR_NET_ADHOC_NOT_CREATED
NW-14163-5	0x8041071d	SCE_ERROR_NET_ADHOC_INVALID_ALIGNMENT
C2-14164-6	0x80102f07	SCE_SCREENSHOT_ERROR_SCREENSHOT_DISABLED
C2-14165-7	0x80102f09	SCE_SCREENSHOT_ERROR_CAPTURE_BUSY
C2-14166-8	0x80102f0a	SCE_SCREENSHOT_ERROR_CAPTURE_CANCELED
C0-14473-9	0x805b0029	SCE_GXM_ERROR_RAZOR
C1-14494-2	0x80024b10	SCE_KERNEL_ERROR_MEMBLOCK_LOCKED
C2-14495-3	0x80100606	SCE_APPUTIL_ERROR_PASSCODE_MISMATCH
NP-14496-4	0x80551d12	SCE_NP_BASIC_ERROR_NO_JOIN_GAME_ACK_HANDLER
C2-14497-5	0x80107d01	SCE_TW_DIALOG_ERROR_PARAM
C2-14498-6	0x80107d02	SCE_TW_DIALOG_ERROR_RESERVED
NW-14526-8	0x80410b04	SCE_ERROR_NET_ADHOCCTL_INVALID_ARG
NW-14527-9	0x80410b07	SCE_ERROR_NET_ADHOCCTL_ALREADY_INITIALIZED
NW-14528-0	0x80410b08	SCE_ERROR_NET_ADHOCCTL_NOT_INITIALIZED
C2-14529-1	0x80107d03	SCE_TW_DIALOG_ERROR_NET_UNLOADED
C0-14737-2	0x80620010	SCE_AVCDEC_ERROR_INTERLACED
C1-14738-3	0x80024804	SCE_KERNEL_ERROR_PARTITION_NO_VIRTUAL_ADDRESS
C0-14739-4	0x80580003	SCE_PERF_ERROR_POP_WITHOUT_PUSH
C0-14740-6	0x80580004	SCE_PERF_ERROR_TOO_MANY_PUSHES
C1-14741-7	0x8008c009	SCE_RAZOR_GPU_ERROR_INVALID_POINTER
NW-14763-1	0x8041211e	SCE_NET_CTL_ERROR_PSP_ADHOC_JOIN_TIMEOUT
C2-14764-2	0x8010530f	SCE_MUSIC_EXPORT_ERROR_FILE_EXIST
C2-14765-3	0x80107e01	SCE_NEAR_DIALOG_ERROR_PARAM
C2-14766-4	0x80107e02	SCE_NEAR_DIALOG_ERROR_MODULE
C2-14767-5	0x80107e03	SCE_NEAR_DIALOG_ERROR_INVALID_MODE
C2-14768-6	0x80107e04	SCE_NEAR_DIALOG_ERROR_INVALID_SDK_VERSION
C2-14769-7	0x80107e05	SCE_NEAR_DIALOG_ERROR_INVALID_GIFT_STATUS
C2-14770-9	0x80107e06	SCE_NEAR_DIALOG_ERROR_IN_USE
C2-14771-0	0x80100c08	SCE_NETCHECK_DIALOG_ERROR_INVALID_TIMEOUT_PARAM
NP-14772-1	0x80550f72	SCE_NP_COMMERCE2_ERROR_NOT_SIGNIN
C2-14773-2	0x80101a10	SCE_PHOTO_EXPORT_ERROR_INVALID_DATA
C2-14774-3	0x80102f0d	SCE_SCREENSHOT_ERROR_INVALID_DATA
C2-14775-4	0x80102f0e	SCE_SCREENSHOT_ERROR_NOT_SUPPORTED_DATA
C0-14829-4	0x805b002a	SCE_GXM_ERROR_INVALID_SAMPLER_FILTER_MODE
C0-14830-6	0x805b002b	SCE_GXM_ERROR_INVALID_REGION_CLIP_IN_COMMAND_LIST
C0-14831-7	0x805b002c	SCE_GXM_ERROR_WITHIN_COMMAND_LIST
C0-14832-8	0x805b002d	SCE_GXM_ERROR_NOT_WITHIN_COMMAND_LIST
C1-14848-5	0x8002d020	SCE_KERNEL_ERROR_MODULEMGR_CANNOT_STOP
C2-14997-0	0x80100670	SCE_APPUTIL_ERROR_PSP_SAVEDATA_DATA_BROKEN
C2-14998-1	0x80100671	SCE_APPUTIL_ERROR_PSP_SAVEDATA_FILETYPE_MISMATCH
C2-14999-2	0x80100672	SCE_APPUTIL_ERROR_PSP_SAVEDATA_DATABUF_SIZE
C2-15086-0	0x80107716	SCE_DTCP_IP_ERROR_IPC
C2-15087-1	0x80107717	SCE_DTCP_IP_ERROR_IPC_TIMEOUT
C0-15107-4	0x80820022	SCE_FIOS_ERROR_UNKNOWN SCE_FIOS_KERNEL_ERROR_UNKNOWN
C0-15108-5	0x80820023	SCE_FIOS_ERROR_ALREADY_EXISTS SCE_FIOS_KERNEL_ERROR_ALREADY_EXISTS

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-15126-5	0x8002200b	SCE_KERNEL_ERROR_CPU_MMU_L1PTE_NOT_FAULT
C1-15127-6	0x8002200c	SCE_KERNEL_ERROR_CPU_MMU_L2PTE_NOT_FAULT
C1-15128-7	0x8002450f	SCE_KERNEL_ERROR_UID_CLASS_NOT_FOUND
C1-15129-8	0x80028225	SCE_KERNEL_ERROR_MSG_PIPE_ASYNC_REQUEST_OVF
C1-15130-0	0x8002d021	SCE_KERNEL_ERROR_MODULEMGR_ALREADY_LOADED
C1-15131-1	0x8002d022	SCE_KERNEL_ERROR_MODULEMGR_STOPPED
C0-15132-2	0x80580005	SCE_PERF_ERROR_NOT_INITIALIZED
NW-15145-6	0x8041280d	SCE_GAME_UPDATE_ERROR_SERVER_MAINTENANCE
C2-15147-8	0x80104925	SCE_NEAR_ERROR_INVALID_GIFT_ID
C2-15148-9	0x80104926	SCE_NEAR_ERROR_INVALID_GIFT_INFO2
C2-15149-0	0x80100c09	SCE_NETCHECK_DIALOG_ERROR_PSN_AGE_RESTRICTION
C0-15231-2	0x805b002e	SCE_GXM_ERROR_BUFFER_OVERRUN
C1-15232-3	0x8002d023	SCE_KERNEL_ERROR_MODULEMGR_NOT_MAIN_MODULE
C0-15233-4	0x80580006	SCE_PERF_ERROR_ALREADY_STARTED
C0-15234-5	0x80580007	SCE_PERF_ERROR_CANNOT_START
C0-15235-6	0x80580008	SCE_PERF_ERROR_ALREADY_STOPPED
C0-15236-7	0x80580013	SCE_PERF_ERROR_CANNOT_STOP
C4-15298-5	0x80340020	SCE_CTRL_ERROR_NO_DEVICE
C4-15299-6	0x80340021	SCE_CTRL_ERROR_NOT_SUPPORTED
C4-15300-9	0x80340022	SCE_CTRL_ERROR_INVALID_MODE
C4-15301-0	0x80290009	SCE_DISPLAY_ERROR_NO_OUTPUT_SIGNAL
C1-15302-1	0x80024510	SCE_KERNEL_ERROR_UID_LINK_COUNT_UNDERFLOW
C1-15303-2	0x80024e03	SCE_KERNEL_ERROR_NONAMEHEAP
C1-15304-3	0x8002710c	SCE_KERNEL_ERROR_ILLEGAL_SYSCALL_NUMBER
C1-15305-4	0x80020436	SCE_COMMON_DIALOG_ERROR_GXM_IS_UNINITIALIZED
C2-15306-5	0x80108301	SCE_MP4REC_ERROR_INVALID_ARG
C2-15307-6	0x80108302	SCE_MP4REC_ERROR_OUT_OF_MEMORY
C2-15308-7	0x80108303	SCE_MP4REC_ERROR_INVALID_RECMODE
C2-15309-8	0x80108304	SCE_MP4REC_ERROR_INVALID_BUFSIZE
C2-15310-0	0x80108305	SCE_MP4REC_ERROR_NOT_INITIALIZED
C2-15311-1	0x80108306	SCE_MP4REC_ERROR_DURATION_LIMIT
C2-15312-2	0x80108307	SCE_MP4REC_ERROR_INTERNAL
C2-15313-3	0x80108308	SCE_MP4REC_ERROR_NOSPACE
C2-15314-4	0x80108309	SCE_MP4REC_ERROR_STATE
C2-15315-5	0x80108342	SCE_MP4REC_ERROR_VIDEOENC_INVALID_PARAM
C2-15316-6	0x80108343	SCE_MP4REC_ERROR_VIDEOENC_OUT_OF_MEMORY
C2-15317-7	0x80108344	SCE_MP4REC_ERROR_VIDEOENC_INVALID_STATE
C2-15318-8	0x80108345	SCE_MP4REC_ERROR_VIDEOENC_UNSUPPORTED_IMAGE_SIZE
C2-15319-9	0x80108346	SCE_MP4REC_ERROR_VIDEOENC_INVALID_COLOR_FORMAT
C2-15320-1	0x80108347	SCE_MP4REC_ERROR_VIDEOENC_NOT_PHY_CONTINUOUS_MEMORY
C2-15321-2	0x80108348	SCE_MP4REC_ERROR_VIDEOENC_ALREADY_USED
C2-15322-3	0x80108349	SCE_MP4REC_ERROR_VIDEOENC_INVALID_POINTER
C2-15323-4	0x8010834b	SCE_MP4REC_ERROR_VIDEOENC_INITIALIZE
C2-15324-5	0x8010834c	SCE_MP4REC_ERROR_VIDEOENC_NOT_INITIALIZE
C2-15325-6	0x8010834e	SCE_MP4REC_ERROR_VIDEOENC_INVALID_ARGUMENT_SIZE
C2-15326-7	0x80108352	SCE_MP4REC_ERROR_AVCENC_INVALID_PARAM
C2-15327-8	0x80108353	SCE_MP4REC_ERROR_AVCENC_OUT_OF_MEMORY
C2-15328-9	0x80108354	SCE_MP4REC_ERROR_AVCENC_INVALID_STATE
C2-15329-0	0x80108355	SCE_MP4REC_ERROR_AVCENC_UNSUPPORTED_IMAGE_SIZE
C2-15330-2	0x80108356	SCE_MP4REC_ERROR_AVCENC_INVALID_COLOR_FORMAT
C2-15331-3	0x80108357	SCE_MP4REC_ERROR_AVCENC_NOT_PHY_CONTINUOUS_MEMORY
C2-15332-4	0x80108358	SCE_MP4REC_ERROR_AVCENC_ALREADY_USED
C2-15333-5	0x80108359	SCE_MP4REC_ERROR_AVCENC_INVALID_POINTER
C2-15334-6	0x8010835a	SCE_MP4REC_ERROR_AVCENC_PICTURE_BUFFER_FULL
C2-15335-7	0x8010835b	SCE_MP4REC_ERROR_AVCENC_INITIALIZE
C2-15336-8	0x8010835c	SCE_MP4REC_ERROR_AVCENC_NOT_INITIALIZE
C2-15337-9	0x8010835d	SCE_MP4REC_ERROR_AVCENC_INVALID_ENCODE_PARAM

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-15338-0	0x8010835e	SCE_MP4REC_ERROR_AVCENC_INVALID_ARGUMENT_SIZE
C2-15339-1	0x80108361	SCE_MP4REC_ERROR_AVCENC_MAXAUSIZE
C2-15340-3	0x80108381	SCE_MP4REC_ERROR_AACENC_INVALIDARG
C2-15341-4	0x80108382	SCE_MP4REC_ERROR_AACENC_INVALIDHANDLE
C2-15342-5	0x80108383	SCE_MP4REC_ERROR_AACENC_OUTOFMEMORY
C2-15343-6	0x80108384	SCE_MP4REC_ERROR_AACENC_INTERNAL
C2-15344-7	0x80108385	SCE_MP4REC_ERROR_AACENC_FRAME_LIMIT
C2-15345-8	0x80108386	SCE_MP4REC_ERROR_AACENC_NOTIMPL
C2-15346-9	0x801083a1	SCE_MP4REC_ERROR_AVREC_OUT_OF_MEMORY
C2-15347-0	0x801083a2	SCE_MP4REC_ERROR_AVREC_FATAL
C2-15348-1	0x801083a3	SCE_MP4REC_ERROR_AVREC_INVALID_VALUE
C2-15349-2	0x801083a4	SCE_MP4REC_ERROR_AVREC_VENC_BUFFER_FULL
C2-15350-4	0x801083a5	SCE_MP4REC_ERROR_AVREC_FILE_ACCESS
C2-15351-5	0x801083a6	SCE_MP4REC_ERROR_AVREC_FILE_OPERATION
C2-15352-6	0x801083a7	SCE_MP4REC_ERROR_AVREC_NOT_IMPLEMENT
C2-15353-7	0x801083a8	SCE_MP4REC_ERROR_AVREC_BUFFER_FULL
C2-15354-8	0x801083a9	SCE_MP4REC_ERROR_AVREC_SAMPLE_NUM_BUFFER_FULL
C2-15355-9	0x801083aa	SCE_MP4REC_ERROR_AVREC_VIDEO_BUFFER_FULL
C2-15356-0	0x801083ab	SCE_MP4REC_ERROR_AVREC_VIDEO_SAMPLE_NUM_BUFFER_FULL
C2-15357-1	0x801083ac	SCE_MP4REC_ERROR_AVREC_AUDIO_BUFFER_FULL
C2-15358-2	0x801083ad	SCE_MP4REC_ERROR_AVREC_AUDIO_SAMPLE_NUM_BUFFER_FULL
C2-15359-3	0x801083ae	SCE_MP4REC_ERROR_AVREC_VENC_RET_INVALID_POINTER
C2-15360-5	0x801083b1	SCE_MP4REC_ERROR_AVREC_NAACENC_INVALIDARG
C2-15361-6	0x801083b2	SCE_MP4REC_ERROR_AVREC_NAACENC_INVALIDHANDLE
C2-15362-7	0x801083b3	SCE_MP4REC_ERROR_AVREC_NAACENC_OUTOFMEMORY
C2-15363-8	0x801083b4	SCE_MP4REC_ERROR_AVREC_NAACENC_INTERNAL
C2-15364-9	0x801083b5	SCE_MP4REC_ERROR_AVREC_NAACENC_FRAME_LIMIT
C2-15365-0	0x801083b6	SCE_MP4REC_ERROR_AVREC_NAACENC_NOTIMPL
C2-15366-1	0x801083b7	SCE_MP4REC_ERROR_AVREC_NAACENC_FATAL
C2-15367-2	0x801083c1	SCE_MP4REC_ERROR_AVREC_FF4_ARGS
C2-15368-3	0x801083c2	SCE_MP4REC_ERROR_AVREC_FF4_STATE
C2-15369-4	0x801083c3	SCE_MP4REC_ERROR_AVREC_FF4_NOMEM
C2-15370-6	0x801083c4	SCE_MP4REC_ERROR_AVREC_FF4_FILE
C2-15371-7	0x801083c5	SCE_MP4REC_ERROR_AVREC_FF4_NOTFOUND
C2-15372-8	0x801083c6	SCE_MP4REC_ERROR_AVREC_FF4_OVERFLOW
C2-15373-9	0x801083c7	SCE_MP4REC_ERROR_AVREC_FF4_FORMAT
C2-15374-0	0x801083c8	SCE_MP4REC_ERROR_AVREC_FF4_INTERNAL
C2-15375-1	0x801083c9	SCE_MP4REC_ERROR_AVREC_FF4_FATAL
C2-15376-2	0x801083e1	SCE_MP4REC_ERROR_EXPORT_PARAM
C2-15377-3	0x801083e2	SCE_MP4REC_ERROR_EXPORT_FILE_NOT_FOUND
C2-15378-4	0x801083e3	SCE_MP4REC_ERROR_EXPORT_CONTENT_FULL
C2-15379-5	0x801083e4	SCE_MP4REC_ERROR_EXPORT_NO_MEMORY
C2-15380-7	0x801083e5	SCE_MP4REC_ERROR_EXPORT_SERVER_DOWN
C2-15381-8	0x801083e6	SCE_MP4REC_ERROR_EXPORT_TOO_MANY_CLIENT
C2-15382-9	0x801083e7	SCE_MP4REC_ERROR_EXPORT_MEDIA_FULL
C2-15383-0	0x801083e8	SCE_MP4REC_ERROR_EXPORT_CREATE_FILE
C2-15384-1	0x801083e9	SCE_MP4REC_ERROR_EXPORT_NOT_SUPPORTED_FORMAT
C2-15385-2	0x801083ea	SCE_MP4REC_ERROR_EXPORT_CANCELED
C2-15386-3	0x801083eb	SCE_MP4REC_ERROR_EXPORT_MEDIA_NOT_EXIST
C2-15387-4	0x801083ec	SCE_MP4REC_ERROR_EXPORT_DB_CORRUPTED
C2-15388-5	0x801083ed	SCE_MP4REC_ERROR_EXPORT_FILE_EXIST
C2-15389-6	0x801083ee	SCE_MP4REC_ERROR_EXPORT_INTERNAL
NP-15390-8	0x80552308	SCE_NP_ACTIVITY_ERROR_INVALID_APP_VER
NP-15391-9	0x80552309	SCE_NP_ACTIVITY_ERROR_INVALID_APP_PARAM
C2-15392-0	0x80108401	SCE_TELEPORT_ERROR_FATAL
C2-15393-1	0x80108402	SCE_TELEPORT_ERROR_PARAM
C2-15394-2	0x80108403	SCE_TELEPORT_ERROR_NOT_INITIALIZED

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C2-15395-3	0x80108404	SCE TELEPORT ERROR ALREADY INITIALIZED
C2-15396-4	0x80108405	SCE TELEPORT ERROR STATE
C2-15397-5	0x80108406	SCE TELEPORT ERROR XML PARSE
C2-15398-6	0x80108407	SCE TELEPORT ERROR NO MEMORY
C2-15399-7	0x80108408	SCE TELEPORT ERROR CONNECTION TIMEOUT
C2-15400-0	0x80108409	SCE TELEPORT ERROR COMMUNICATION
C2-15401-1	0x8010840a	SCE TELEPORT ERROR NOT SUPPORTED PLATFORM
C1-15453-8	0x80024b11	SCE KERNEL ERROR NO SMB
C2-15454-9	0x801006a0	SCE APPUTIL ERROR STACKSIZE TOO SHORT
C2-15456-1	0x801083ef	SCE MP4REC ERROR EXPORT NOT INITIALIZED
C2-15457-2	0x801083f0	SCE MP4REC ERROR EXPORT OPEN FAILED
C2-15458-3	0x801083f1	SCE MP4REC ERROR EXPORT NOT ENOUGH AREA
C2-15459-4	0x801083f2	SCE MP4REC ERROR EXPORT NOT VALID STR
C2-15460-6	0x801083f3	SCE MP4REC ERROR EXPORT NOT VALID FILENAME
C2-15461-7	0x80108430	SCE TELEPORT ERROR LAUNCH FAILED INVALID PASSCODE
C2-15462-8	0x80108431	SCE TELEPORT ERROR LAUNCH FAILED OTHER APP FG
C2-15463-9	0x80108432	SCE TELEPORT ERROR LAUNCH FAILED OTHER APP BG
C2-15464-0	0x80108433	SCE TELEPORT ERROR LAUNCH FAILED APP REFUSED
C2-15465-1	0x80108434	SCE TELEPORT ERROR LAUNCH FAILED
C2-15466-2	0x80108435	SCE TELEPORT ERROR DELETE FAILED FORBIDDEN
C2-15467-3	0x80108436	SCE TELEPORT ERROR DELETE FAILED
C2-15468-4	0x80108437	SCE TELEPORT ERROR LAUNCH FAILED INTERNAL
NP-15549-4	0x80552901	SCE NP WEBAPI ERROR OUT OF MEMORY
NP-15550-6	0x80552902	SCE NP WEBAPI ERROR INVALID ARGUMENT
NP-15551-7	0x80552903	SCE NP WEBAPI ERROR INVALID LIB CONTEXT ID
NP-15552-8	0x80552904	SCE NP WEBAPI ERROR LIB CONTEXT NOT FOUND
NP-15553-9	0x80552905	SCE NP WEBAPI ERROR USER CONTEXT NOT FOUND
NP-15554-0	0x80552906	SCE NP WEBAPI ERROR REQUEST NOT FOUND
NP-15555-1	0x80552907	SCE NP WEBAPI ERROR NOT SIGNED IN
NP-15556-2	0x80552908	SCE NP WEBAPI ERROR INVALID CONTENT PARAMETER
NP-15557-3	0x80552909	SCE NP WEBAPI ERROR ABORTED
NP-15558-4	0x8055290a	SCE NP WEBAPI ERROR USER CONTEXT ALREADY EXIST
NP-15559-5	0x8055290b	SCE NP WEBAPI ERROR PUSH EVENT FILTER NOT FOUND
NP-15560-7	0x8055290c	SCE NP WEBAPI ERROR PUSH EVENT CALLBACK NOT FOUND
NP-15561-8	0x8055290d	SCE NP WEBAPI ERROR HANDLE NOT FOUND
NP-15562-9	0x8055290e	SCE NP WEBAPI ERROR SERVICE_PUSH_EVENT_FILTER_NOT_FOUND
NP-15563-0	0x8055290f	SCE NP WEBAPI ERROR SERVICE_PUSH_EVENT_CALLBACK_NOT_FOUND
NP-15564-1	0x80552910	SCE NP WEBAPI ERROR SIGNED IN USER NOT FOUND
NP-15565-2	0x80552911	SCE NP WEBAPI ERROR LIB CONTEXT BUSY
NP-15566-3	0x80552912	SCE NP WEBAPI ERROR USER CONTEXT BUSY
NP-15567-4	0x80552913	SCE NP WEBAPI ERROR REQUEST BUSY
NP-15568-5	0x80552914	SCE NP WEBAPI ERROR INVALID HTTP STATUS CODE
C1-15608-0	0x80028187	SCE KERNEL ERROR LW MUTEX CAN NOT ACCESS
C2-15630-5	0x80108801	SCE NP FRIENDLIST2 DIALOG ERROR INVALID PARAM
C2-15631-6	0x80108802	SCE NP FRIENDLIST2 DIALOG_ERROR_REQUIRED_MODULES_NOT_LOADED
C2-15632-7	0x80108803	SCE NP FRIENDLIST2 DIALOG ERROR NOT SIGNED IN
C2-15633-8	0x80108804	SCE NP FRIENDLIST2 DIALOG_ERROR_LACK_OF_LIBHTTP_POOL_SIZE
C2-15634-9	0x80108805	SCE NP FRIENDLIST2 DIALOG_ERROR_LACK_OF_LIBSSL_POOL_SIZE
C2-15635-0	0x80108806	SCE NP FRIENDLIST2 DIALOG ERROR INTERNAL ERROR
C0-15883-5	0x807f0013	SCE AUDIODEC ERROR BUSY
C1-15892-5	0x8002430b	SCE KERNEL ERROR PHYMEMPART NOT ACTIVE
C1-15893-6	0x80024905	SCE KERNEL ERROR HEAP NOT ACTIVE

©SCEI

SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C0-15894-7	0x80920101	SCE_JSON_ERROR_PARSE_INVALID_CHAR
C0-15895-8	0x80920102	SCE_JSON_ERROR_NOMEM
C0-15896-9	0x80920103	SCE_JSON_ERROR_NOFILE
C0-15897-0	0x80920104	SCE_JSON_ERROR_NOROOT
C0-15898-1	0x80920110	SCE_JSON_ERROR_NOINIT
C0-15899-2	0x80920111	SCE_JSON_ERROR_MULTIPLEINIT
NP-15907-2	0x80552915	SCE_NP_WEBAPI_ERROR_PROHIBITED_HTTP_HEADER
NP-15908-3	0x80552916	SCE_NP_WEBAPI_ERROR_PROHIBITED_FUNCTION_CALL
NP-15909-4	0x80552917	SCE_NP_WEBAPI_ERROR_MULTIPART_PART_NOT_FOUND
NP-15910-6	0x80552918	SCE_NP_WEBAPI_ERROR_PARAMETER_TOO_LONG
NP-15911-7	0x80552a01	SCE_NP_WEBAPI_ERROR_NOT_INITIALIZED
NP-15912-8	0x80552a02	SCE_NP_WEBAPI_ERROR_ALREADY_INITIALIZED
NP-15913-9	0x80552a03	SCE_NP_WEBAPI_ERROR_SSL_ERR_CN_CHECK
NP-15914-0	0x80552a04	SCE_NP_WEBAPI_ERROR_SSL_ERR_UNKNOWN_CA
NP-15915-1	0x80552a05	SCE_NP_WEBAPI_ERROR_SSL_ERR_NOT_AFTER_CHECK
NP-15916-2	0x80552a06	SCE_NP_WEBAPI_ERROR_SSL_ERR_NOT_BEFORE_CHECK
NP-15917-3	0x80552a07	SCE_NP_WEBAPI_ERROR_SSL_ERR_INVALID_CERT
NP-15918-4	0x80552a08	SCE_NP_WEBAPI_ERROR_SSL_ERR_INTERNAL
C2-15920-7	0x80108438	SCE_TELEPORT_ERROR_LAUNCH_FAILED_VITATV_NEED_UPDATE
C4-17015-4	0x8036020b	SCE_MOTION_ERROR_INVALID_ARG
C0-17117-7	0x80920105	SCE_JSON_ERROR_NOBUF
NP-17187-4	0x80552509	SCE_NP_PARTY_ERROR_GAME_SESSION_NOT_ENABLED
NP-17188-5	0x80552510	SCE_NP_PARTY_ERROR_OPERATION_IN_PROGRESS
NP-17189-6	0x80552919	SCE_NP_WEBAPI_ERROR_HANDLE_BUSY
NP-17190-8	0x8055291a	SCE_NP_WEBAPI_ERROR_LIB_CONTEXT_MAX
NP-17191-9	0x8055291b	SCE_NP_WEBAPI_ERROR_USER_CONTEXT_MAX
NP-17192-0	0x80552a09	SCE_NP_WEBAPI_ERROR_TITLE_IS_BANNED
C4-17528-3	0x802e0000	SCE_CAMERA_ERROR_PARAM
C0-17537-3	0x80820000	SCE_FIOS_ERROR_UNIMPLEMENTED SCE_FIOS_KERNEL_ERROR_UNIMPLEMENTED
C0-17540-7	0x80420000	SCE_SAS_ERROR_FAIL
C0-17624-0	0x80630000	SCE_ATRAC_ERROR_INVALID_POINTER
C0-17625-1	0x807f0000	SCE_AUDIODEC_ERROR_API_FAIL
C0-17626-2	0x80860000	SCE_AUDIOENC_ERROR_API_FAIL
C0-17629-5	0x80600000	SCE_CODECEENGINE_ERROR_INVALID_POINTER
C1-17630-7	0x800a0000	SCE_COREDUMP_ERROR_PARAM
C4-17631-8	0x80290000	SCE_DISPLAY_ERROR_INVALID_HEAD
C0-17632-9	0x80570000	SCE_DBGFONT_ERROR_NOT_INIT
C0-17633-0	0x804f0000	SCE_HEAP_ERROR_INVALID_ID
C0-17634-1	0x80580000	SCE_PERF_ERROR_INVALID_ARGUMENT
C4-17635-2	0x802b0000	SCE_POWER_ERROR_INVALID_VALUE
C2-17644-2	0x80109301	SCE_GAME_CUSTOM_DATA_DIALOG_ERROR_LACK_OF_LIBHTTP_POOL_SIZE
C2-17645-3	0x80109302	SCE_GAME_CUSTOM_DATA_DIALOG_ERROR_LACK_OF_LIBSSL_POOL_SIZE
C2-17646-4	0x80109201	SCE_INVITATION_DIALOG_ERROR_LACK_OF_LIBHTTP_POOL_SIZE
C2-17647-5	0x80109202	SCE_INVITATION_DIALOG_ERROR_LACK_OF_LIBSSL_POOL_SIZE
NP-17648-6	0x8055291c	SCE_NP_WEBAPI_ERROR_EXTD_PUSH_EVENT_FILTER_NOT_FOUND
NP-17649-7	0x8055291d	SCE_NP_WEBAPI_ERROR_EXTD_PUSH_EVENT_CALLBACK_NOT_FOUND
C0-17650-9	0x80850000	SCE_XML_ERROR_GENERIC_ERROR
C0-17653-2	0x805b0000	SCE_GXM_ERROR_UNINITIALIZED
C0-17654-3	0x805d0000	SCE_GXT_ERROR_INVALID_VALUE
C1-17693-6	0x8002d0f3	SCE_KERNEL_ERROR_MODULEMGR_INHIBITED

©SCEI



SCE CONFIDENTIAL

Short Error Code	Hexadecimal Error Code	Macro
C1-17694-7	0x8008080d	SCE_KERNEL_ERROR_DEC14P_ILLEGAL_PARAM
C1-17695-8	0x8008080e	SCE_KERNEL_ERROR_DEC14P_INTERRUPTED
C1-17696-9	0x8008080f	SCE_KERNEL_ERROR_DEC14P_HOST_PROCESS_DISABLED
C1-17697-0	0x80080810	SCE_KERNEL_ERROR_DEC14P_HOST_CREATE_PROCESS
C1-17698-1	0x80080811	SCE_KERNEL_ERROR_DEC14P_HOST_TOOMANY_PROCESS
NP-17705-0	0x80552a0a	SCE_NP_WEBAPI_ERROR_NP_TITLE_DAT_NOT_FOUND
NP-17706-1	0x80552a0b	SCE_NP_WEBAPI_ERROR_TITLE_ID_NOT_MATCHED_TO_NP_TITLE_ID
C2-17736-4	0x80100686	SCE_APPUTIL_ERROR_MOUNT_LIMIT_OVER
NP-17737-5	0x8055291e	SCE_NP_WEBAPI_ERROR_AFTER_SEND

000004892117