

Camera Import Dialog Reference

© 2012 Sony Computer Entertainment Inc.
All Rights Reserved.
SCE Confidential

Table of Contents

| | |
|--|-----------|
| Call | 3 |
| sceCameraImportDialogParamInit | 4 |
| sceCameraImportDialogInit | 5 |
| SceCameraImportDialogParam | 7 |
| SceCameraImportDialogMemoryRawParam | 11 |
| SceCameraImportDialogMemoryJpegParam | 13 |
| SceCameraImportDialogOverlayImage | 14 |
| Retrieval of Operation Status | 16 |
| sceCameraImportDialogGetStatus | 17 |
| Retrieval of Call Result..... | 18 |
| sceCameraImportDialogGetResult | 19 |
| SceCameraImportDialogResult | 20 |
| SceCameraImportDialogOutputParam | 21 |
| Abortion..... | 23 |
| sceCameraImportDialogAbort..... | 24 |
| Termination | 25 |
| sceCameraImportDialogTerm | 26 |
| Constants | 27 |
| Return Codes | 28 |

SCE CONFIDENTIAL

Call

000004892117

Document serial number: 000004892117

SCE CONFIDENTIAL

sceCameraImportDialogParamInit

Macro for call parameter initialization

Definition

```
#include <cameraimport_dialog.h>
static inline
void sceCameraImportDialogParamInit(SceCameraImportDialogParam *param)
{
    sceClibMemset(param, 0x0, sizeof(SceCameraImportDialogParam));
    _sceCommonDialogSetMagicNumber(&param->commonParam);
    param->sdkVersion = SCE_PSP2_SDK_VERSION;
}
```

Arguments

param Call parameter

Return Values

None

Description

This is a macro function for initializing the Camera Import Dialog call parameter.

Before performing the various call parameter settings, be sure to use this macro to execute structure initialization. The appropriate SDK version is set at the same time.

See Also

SceCameraImportDialogParam

SCE CONFIDENTIAL

sceCameraImportDialogInit

Call various functions of Camera Import Dialog

Definition

```
#include <cameraimport_dialog.h>
SceInt32 sceCameraImportDialogInit(
    const SceCameraImportDialogParam *param
)
```

Arguments

param Call parameter

Return Values

Returns SCE_OK (0) as the value of the function for success.

Returns one of the following error codes (negative value) for errors.

| Value | Hexadecimal | Description |
|--|-------------|--|
| SCE_COMMON_DIALOG_ERROR_BUSY | 0x80020401 | The Common Dialog function is already being called (details below) |
| SCE_COMMON_DIALOG_ERROR_NULL | 0x80020402 | NULL was specified for the <i>param</i> argument |
| SCE_COMMON_DIALOG_ERROR_INVALID_ARGUMENT | 0x80020403 | Invalid value was specified for the <i>param</i> argument |
| SCE_COMMON_DIALOG_ERROR_INVALID_INFOBAR_PARAM | 0x80020433 | Invalid value was specified for <i>infobarParam</i> which is a member of the <i>param</i> argument |
| SCE_COMMON_DIALOG_ERROR_INVALID_BG_COLOR | 0x80020434 | Invalid value was specified for <i>bgColor</i> which is a member of the <i>param</i> argument |
| SCE_COMMON_DIALOG_ERROR_INVALID_DIMMER_COLOR | 0x80020435 | Invalid value was specified for <i>dimmerColor</i> which is a member of the <i>param</i> argument |
| SCE_COMMON_DIALOG_ERROR_UNEXPECTED_FATAL | 0x8002047F | Internal error |
| SCE_CAMERAIMPORT_DIALOG_ERROR_INVALID_WORKING_BUFFER | 0x80104702 | The <i>workingBuffer</i> and <i>workingBufferSize</i> members of the argument <i>param</i> do not meet limitations |
| SCE_CAMERAIMPORT_DIALOG_ERROR_REQUIRED_PRX_IS_NOT_LOADED | 0x80104703 | The PRX required for running Camera Import Dialog has not been loaded. |

Description

This function calls the Camera Import Dialog function.

This function can be called only when other Common Dialog functions are not called (including the function of Camera Import Dialog proper). If this function is called at times other than the above, `SCE_COMMON_DIALOG_ERROR_BUSY` is returned.

When calling this function is successful, the operation status immediately changes to `SCE_COMMON_DIALOG_STATUS_RUNNING`. For details on the operation statuses, refer to the `sceCameraImportDialogGetStatus()` section.

In *param*, specify the call parameter structure for which the camera resolution, camera device (front/rear), photograph data format, etc. available to the user were set.

Be sure to set values for *param* after performing initialization with the `sceCameraImportDialogParamInit()` macro.

The *param* instance need not be allocated after this function is called, but some of the pointer reference parameters must be held until calling of the Camera Import Dialog function is ended by calling `sceCameraImportDialogTerm()`.

This function is multithread safe.

See Also

`SceCameraImportDialogParam`, `sceCameraImportDialogParamInit()`,
`sceCameraImportDialogGetStatus()`

SCE CONFIDENTIAL

SceCameraImportDialogParam

Structure for calling Camera Import Dialog

Definition

```
#include <cameraimport_dialog.h>
typedef struct SceCameraImportDialogParam {
    SceUInt32 sdkVersion;
    SceCommonDialogParam commonParam;
    SceUInt32 outputMode;
    SceCameraImportDialogMemoryRawParam *memRawParam;
    SceCameraImportDialogMemoryJpegParam *memJpegParam;
    SceChar8 reserved1[8];
    void *workingBuffer;
    SceInt32 workingBufferSize;
    SceUInt32 availableResolution;
    SceUInt32 initialResolution;
    SceUInt32 availableDevice;
    SceUInt32 initialDevice;
    SceUInt32 rotationMode;
    SceUInt32 overlayMode;
    SceCameraImportDialogOverlayImage *overlayImage;
    SceChar8 reserved2[48];
} SceCameraImportDialogParam;
```

Members

| | |
|----------------------------|--|
| <i>sdkVersion</i> | SDK version |
| <i>commonParam</i> | Common parameters for Common Dialogs |
| <i>outputMode</i> | Photograph data output format |
| <i>memRawParam</i> | Parameter for RAW format output |
| <i>memJpegParam</i> | Parameter for JPEG format output |
| <i>reserved1</i> | Reserved area (fill with all 0s) |
| <i>workingBuffer</i> | Working buffer |
| <i>workingBufferSize</i> | Size of working buffer |
| <i>availableResolution</i> | Camera resolutions available to the user |
| <i>initialResolution</i> | Camera resolution at the time of dialog start-up |
| <i>availableDevice</i> | Camera devices available to the user |
| <i>initialDevice</i> | Camera device at the time of dialog start-up |
| <i>rotationMode</i> | Vertical/horizontal position determination mode |
| <i>overlayMode</i> | Usage method of overlay images |
| <i>overlayImage</i> | Overlay image |
| <i>reserved2</i> | Reserved area (fill with all 0s) |

Description

This is a structure passed to `sceCameraImportDialogInit()` to determine the operation of Camera Import Dialog. Use `sceCameraImportDialogParamInit()` to initialize it.

Specify the SDK version in `sdkVersion`. An appropriate value is input when the structure is initialized with `sceCameraImportDialogParamInit()`.

Specify the common parameters for Common Dialogs in `commonParam`.

Specify the info bar information in `commonParam.infoBarParam`. Specify NULL in Camera Import Dialog. Always hide the info bar in Camera Import Dialog.

Specify background color information in ARGB format (0 - 255) in `commonParam.bgColor`. For use in the game, only 0 (transparent) or 255 (non-transparent) can be specified in `commonParam.bgColor.a`.

Specify dimmer color information in ARGB format (0 - 255) in `commonParam.dimmerColor`. Only (r,g,b,a)=(0,0,0,0) (transparent) or (r,g,b,a)=(0,0,0,255) (non-transparent black) can be used.

For details on the common parameters for Common Dialogs, refer to the "Common Dialog Reference" document.

Specify the output format of the data of photographs taken in `outputMode`.

| Macro | Value | Description |
|--|-------|--|
| <code>SCE_CAMERAIMPORT_DIALOG_OUTPUT_MODE_MEMORY_RAW</code> | 0 | Outputs photograph data in RAW format |
| <code>SCE_CAMERAIMPORT_DIALOG_OUTPUT_MODE_MEMORY_JPEG</code> | 1 | Outputs photograph data in JPEG format |

`memRawParam` is a structure for specifying the parameters for output in RAW format. Make sure to set its contents if `SCE_CAMERAIMPORT_DIALOG_OUTPUT_MODE_MEMORY_RAW` is specified in `outputMode`. If other values are specified in `outputMode`, assign NULL. For details, refer to the `SceCameraImportDialogMemoryRawParam` section.

`memJpegParam` is a structure for specifying the parameters for output in JPEG format. Make sure to set its contents if `SCE_CAMERAIMPORT_DIALOG_OUTPUT_MODE_MEMORY_JPEG` is specified in `outputMode`. If other values are specified in `outputMode`, assign NULL. For details, refer to the `SceCameraImportDialogMemoryJpegParam` section.

`reserved1` is a reserved area for future function expansion. It must be filled with all 0s. It will be set to 0 when the structure is initialized with `sceCameraImportDialogParamInit()`.

Pass the working buffer to `workingBuffer` and `workingBufferSize`. The required size is defined by the `SCE_CAMERAIMPORT_DIALOG_WORKING_BUFFER_SIZE` constant. Refer to the "Camera Import Dialog Overview" document for working buffer limitations. Keep this memory area until the completion of the calling of the Camera Import Dialog function with `sceCameraImportDialogTerm()`.

| Macro | Value | Description |
|--|-------------|-------------------------------------|
| <code>SCE_CAMERAIMPORT_DIALOG_WORKING_BUFFER_SIZE</code> | 2*1024*1024 | Required size of the working buffer |

Specify the camera resolutions available to the user in `availableResolution`. Specify the macros below with an OR operation. If not allowing the user to switch among resolutions, only specify the macro value for 1 type. This value must not be set to 0.

| Macro | Value | Description |
|--|-------|-------------|
| <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_640X480</code> | 0x01 | 640x480 |
| <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_640X360</code> | 0x02 | 640x360 |
| <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_480X480</code> | 0x04 | 480x480 |

Specify the camera resolution at the time of Camera Import Dialog start-up in *initialResolution*. Specify 1 type among the values specified with an OR operation in *availableResolution*.

Specify the camera devices available to the user (front/rear) in *availableDevice*. Specify the following macros with an OR operation. If not allowing the user to switch among cameras, only specify the macro value for 1 type. This value must not be set to 0.

| Macro | Value | Description |
|---|-------|--|
| SCE_CAMERAIMPORT_DIALOG_CAMERA_DEVICE_FRONT | 0x01 | The camera installed on the same side of the display |
| SCE_CAMERAIMPORT_DIALOG_CAMERA_DEVICE_REAR | 0x02 | The camera installed on the opposite side of the display |

Specify the camera device at the time of Camera Import Dialog start-up in *initialDevice*. Specify 1 type among the values specified with an OR operation in *availableDevice*.

In *rotationMode*, use the following macros to specify whether determination of vertical/horizontal position is to be performed using acceleration sensor information. When SCE_CAMERAIMPORT_DIALOG_ROTATION_MODE_DISABLE is specified, SCE_CAMERAIMPORT_DIALOG_IMAGE_ORIENTATION_NORMAL will always return to the orientation of SceCameraImportDialogOutputParam.

| Macro | Value | Description |
|---|-------|---|
| SCE_CAMERAIMPORT_DIALOG_ROTATION_MODE_DISABLE | 0 | Disable determination of vertical/horizontal position |
| SCE_CAMERAIMPORT_DIALOG_ROTATION_MODE_ENABLE | 1 | Enable determination of vertical/horizontal position |

Specify the usage method of overlay images in *overlayMode*.

| Macro | Value | Description |
|--|-------|--|
| SCE_CAMERAIMPORT_DIALOG_OVERLAY_MODE_NOT_USE | 0 | Overlay images are not used |
| SCE_CAMERAIMPORT_DIALOG_OVERLAY_MODE_DISPLAY | 1 | Overlay images will be displayed on the UI for taking photographs, but overlay images will not be superimposed on output photographic data. |
| SCE_CAMERAIMPORT_DIALOG_OVERLAY_MODE_PRINT | 2 | Overlay images will not be displayed on the UI for taking photographs, but overlay images will be superimposed on output photographic data. |
| SCE_CAMERAIMPORT_DIALOG_OVERLAY_MODE_DISPLAY_AND_PRINT | 3 | Overlay images will be displayed on the UI for taking photographs, and overlay images will be superimposed on output photographic data also. |

overlayImage is a structure for specifying the image to be overlaid. Assign NULL if not using overlay (that is, if SCE_CAMERAIMPORT_DIALOG_OVERLAY_MODE_NOT_USE is specified in *overlayMode*). For details, refer to the SceCameraImportDialogOverlayImage section.

reserved2 is a reserved area for future function expansion. It must be filled with all 0s. It will be set to 0 when the structure is initialized with `sceCameraImportDialogParamInit()`.

SCE CONFIDENTIAL

See Also

sceCameraImportDialogParamInit(), SceCameraImportDialogMemoryRawParam,
SceCameraImportDialogMemoryJpegParam, SceCameraImportDialogOverlayImage

000004892117

SceCameraImportDialogMemoryRawParam

Structure for specifying RAW format output parameters

Definition

```
#include <cameraimport_dialog.h>
typedef struct SceCameraImportDialogMemoryRawParam{
    void* buffer;
    SceSize bufferSize;
    SceGxmTextureType texType;
    SceGxmTextureFormat texFormat;
    SceChar8 reserved[32];
} SceCameraImportDialogMemoryRawParam;
```

Members

buffer Output buffer
bufferSize Size of output buffer
texType Alignment of output data
texFormat Format of output data
reserved Reserved area (fill with all 0s)

Description

This structure is for specifying RAW format output parameters. It is used if `SCE_CAMERAIMPORT_DIALOG_OUTPUT_MODE_MEMORY_RAW` is specified in the *outputMode* of `SceCameraImportDialogParam`.

Specify the output destination of photographic data in *buffer* and *bufferSize*. The size that should be specified in *bufferSize* depends on the resolutions specified in the *availableResolution* of `SceCameraImportDialogParam`. Specify the largest among the required buffer sizes corresponding to the resolutions specified in *availableResolution*.

| Macro | Value | Description |
|--|-------------|--|
| <code>SCE_CAMERAIMPORT_DIALOG_RAW_U8U8U8U8_SIZE_640X480</code> | (640*480*4) | Required buffer size when using <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_640X480</code> |
| <code>SCE_CAMERAIMPORT_DIALOG_RAW_U8U8U8U8_SIZE_640X360</code> | (640*360*4) | Required buffer size when using <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_640X360</code> |
| <code>SCE_CAMERAIMPORT_DIALOG_RAW_U8U8U8U8_SIZE_480X480</code> | (480*480*4) | Required buffer size when using <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_480X480</code> |

In *texType*, specify the alignment of data to be output in the case of memory output. Only the following value is valid. For details, refer to the "GPU User's Guide" and "libgxm Reference" documents.

| Valid enum Value | Description |
|-------------------------------------|---|
| <code>SCE_GXM_TEXTURE_LINEAR</code> | Linear memory layout with implicit stride |

In *texFormat*, specify the format of data to be output in the case of memory output. Only the following value is valid. For details, refer to the "GPU User's Guide" and "libgxm Reference" documents.

| Valid enum Value | Description |
|---|---|
| <code>SCE_GXM_TEXTURE_FORMAT_U8U8U8U8_ABGR</code> | Pixels are written on the memory in U8U8U8U8 format and in ABGR order (little endian) |

SCE CONFIDENTIAL

reserved is a reserved area for future function expansion. It must be filled with all 0s.

See Also

SceCameraImportDialogParam

000004892117

SCE CONFIDENTIAL

SceCameraImportDialogMemoryJpegParam

Structure for specifying JPEG format output parameters

Definition

```
#include <cameraimport_dialog.h>
typedef struct SceCameraImportDialogMemoryJpegParam{
    void* buffer;
    SceSize bufferSize;
    SceChar8 reserved[32];
} SceCameraImportDialogMemoryJpegParam;
```

Members

buffer Output buffer
bufferSize Size of output buffer
reserved Reserved area (fill with all 0s)

Description

This structure is for specifying JPEG format output parameters. It is used if `SCE_CAMERAIMPORT_DIALOG_OUTPUT_MODE_MEMORY_JPEG` is specified in the *outputMode* of `SceCameraImportDialogParam`.

Specify the output destination of photographic data in *buffer* and *bufferSize*. The size that should be specified in *bufferSize* depends on the resolutions specified in the *availableResolution* of `SceCameraImportDialogParam`. Specify the largest among the required buffer sizes corresponding to the resolutions specified in *availableResolution*.

| Macro | Value | Description |
|--|-----------------------|--|
| <code>SCE_CAMERAIMPORT_DIALOG_JPEG_MAX_SIZE_640X480</code> | (640*480*4+(96*1024)) | Required buffer size when using <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_640X480</code> |
| <code>SCE_CAMERAIMPORT_DIALOG_JPEG_MAX_SIZE_640X360</code> | (640*360*4+(96*1024)) | Required buffer size when using <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_640X360</code> |
| <code>SCE_CAMERAIMPORT_DIALOG_JPEG_MAX_SIZE_480X480</code> | (480*480*4+(96*1024)) | Required buffer size when using <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_RESOLUTION_480X480</code> |

However, the above are theoretical maximum values, and file size is normally around a few hundred KBs.

reserved is a reserved area for future function expansion. It must be filled with all 0s.

See Also

`SceCameraImportDialogParam`

SCE CONFIDENTIAL

SceCameraImportDialogOverlayImage

Structure for specifying overlay images

Definition

```
#include <cameraimport_dialog.h>
typedef struct SceCameraImportDialogOverlayImage {
    const void *buffer;
    SceSize bufferSize;
    SceUInt32 width;
    SceUInt32 height;
    SceUInt32 stride;
    SceGxmTextureType texType;
    SceGxmTextureFormat texFormat;
    SceChar8 reserved[32];
} SceCameraImportDialogOverlayImage;
```

Members

buffer Pointer to the image data
bufferSize Size of image data
width Width of image
height Height of image
stride Image data stride (in bytes).
texType Alignment of image data
texFormat Format of image data
reserved Reserved area (fill with all 0s)

Description

This structure is for specifying overlay images.

It is used if values other than `SCE_CAMERAIMPORT_DIALOG_OVERLAY_MODE_NOT_USE` are specified in the *overlayMode* of `SceCameraImportDialogParam`.

Specify the buffer storing the data for overlay images in *buffer* and *bufferSize*. Keep this memory area until the completion of the calling of the Camera Import Dialog function with `sceCameraImportDialogTerm()`.

Specify the width of overlay image data in pixel units in *width*. *width* must not exceed the following value. Also, 0 must not be specified.

| Macro | Value | Description |
|--|-------|--|
| <code>SCE_CAMERAIMPORT_DIALOG_MAX_OVERLAY_IMAGE_WIDTH</code> | 848 | Maximum size of overlay images (width) |

Specify the height of overlay image data in pixel units in *height*. *height* must not exceed the following value. Also, 0 must not be specified.

| Macro | Value | Description |
|---|-------|---|
| <code>SCE_CAMERAIMPORT_DIALOG_MAX_OVERLAY_IMAGE_HEIGHT</code> | 480 | Maximum size of overlay images (height) |

Specify the stride of overlay image data in byte units in *stride*. This is only valid if `SCE_GXM_TEXTURE_LINEAR_STRIDED` is specified in *texType*. Otherwise, specify 0. Refer to the "GPU User's Guide" document for limitations concerning stride values.

Specify the alignment of overlay image data in *texType*. Only the values below are valid. Refer to the "GPU User's Guide" and "libgxv Reference" documents for details on each value. Implicit stride value will be adopted if SCE_GXM_TEXTURE_LINEAR is specified

| Valid enum Values | Description |
|--------------------------------|--|
| SCE_GXM_TEXTURE_LINEAR | Linear memory layout with implicit stride |
| SCE_GXM_TEXTURE_LINEAR_STRIDED | Linear memory layout with explicit stride values |

Specify the format of overlay images in *texFormat*. Only the value below is valid. For details, refer to the "GPU User's Guide" and "libgxv Reference" documents.

| Valid enum Values | Description |
|--------------------------------------|--|
| SCE_GXM_TEXTURE_FORMAT_U8U8U8U8_ABGR | Pixels are read from the memory in U8U8U8U8 format and in ABGR order (little endian) |

reserved is a reserved area for future function expansion. It must be filled with all 0s.

See Also

SceCameraImportDialogParam

Retrieval of Operation Status

SCE CONFIDENTIAL

sceCameraImportDialogGetStatus

Get operation status of Camera Import Dialog

Definition

```
#include <cameraimport_dialog.h>
SceCommonDialogStatus sceCameraImportDialogGetStatus()
```

Arguments

None

Return Values

Returns one of the following operation statuses as the value of the function.

| Value | Hexadecimal | Description |
|-----------------------------------|-------------|---|
| SCE_COMMON_DIALOG_STATUS_NONE | 0x0 | Camera Import Dialog is not running |
| SCE_COMMON_DIALOG_STATUS_RUNNING | 0x1 | Camera Import Dialog is running |
| SCE_COMMON_DIALOG_STATUS_FINISHED | 0x2 | Camera Import Dialog operation has finished |

Description

This function gets the operation status of Camera Import Dialog.

The default value of the operation status is SCE_COMMON_DIALOG_STATUS_NONE.

When calling `sceCameraImportDialogInit()` is successful, the operation status immediately changes to SCE_COMMON_DIALOG_STATUS_RUNNING.

The operation status of Camera Import Dialog will not change to SCE_COMMON_DIALOG_STATUS_FINISHED before either the user either takes or cancels a photograph or the application calls `sceCameraImportDialogAbort()`.

`sceCameraImportDialogTerm()` can be called only while the operation status is SCE_COMMON_DIALOG_STATUS_FINISHED.

When `sceCameraImportDialogTerm()` is called, the operation status immediately changes to SCE_COMMON_DIALOG_STATUS_NONE.

This function is multithread safe.

See Also

`sceCameraImportDialogInit()`, `sceCameraImportDialogAbort()`,
`sceCameraImportDialogGetResult()`, `sceCameraImportDialogTerm()`

Retrieval of Call Result

SCE CONFIDENTIAL

sceCameraImportDialogGetResult

Get call result of Camera Import Dialog

Definition

```
#include <cameraimport_dialog.h>
SceInt32 sceCameraImportDialogGetResult(
    SceCameraImportDialogResult* result
)
```

Arguments

result Stores the call result

Return Values

Returns SCE_OK (0) as the value of the function for success.

Returns one of the following error codes (negative value) for errors.

| Value | Hexadecimal | Description |
|--|-------------|---|
| SCE_COMMON_DIALOG_ERROR_NULL | 0x80020402 | NULL was specified in the argument <i>result</i> |
| SCE_COMMON_DIALOG_ERROR_INVALID_ARGUMENT | 0x80020403 | Parameter error (details below) |
| SCE_COMMON_DIALOG_ERROR_NOT_FINISHED | 0x80020410 | Called during other than the appropriate operation status (details below) |
| SCE_COMMON_DIALOG_ERROR_UNEXPECTED_FATAL | 0x8002047F | Internal error |

Description

This function retrieves the call result of Camera Import Dialog.

This function can be called only while the operation status of Camera Import Dialog is SCE_COMMON_DIALOG_STATUS_FINISHED. If it is called at times other than the above, SCE_COMMON_DIALOG_ERROR_NOT_FINISHED is returned. For details on the operation statuses, refer to the sceCameraImportDialogGetStatus() section.

The call result of Camera Import Dialog is stored in *result*. For details on the call results, refer to the SceCameraImportDialogResult.

This function is multithread safe.

See Also

SceCameraImportDialogResult, sceCameraImportDialogGetStatus()

SCE CONFIDENTIAL

SceCameraImportDialogResult

Structure for retrieving Camera Import Dialog call result

Definition

```
#include <cameraimport_dialog.h>
typedef struct SceCameraImportDialogResult {
    SceInt32 result;
    SceCameraImportDialogOutputParam output;
    SceChar8 reserved[32];
} SceCameraImportDialogResult;
```

Members

result Stores the call result
output Supplementary photographic image information
reserved Reserved area (fill with all 0s)

Description

This structure receives the Camera Import Dialog call result. It is passed to `sceCameraImportDialogGetResult()`. Fill it with all 0s during initialization.

The call result of Camera Import Dialog is stored in *result*. In the case of success, one of the following positive values is stored.

| Value | Hexadecimal | Description |
|--|-------------|--|
| SCE_COMMON_DIALOG_RESULT_OK | 0x0 | User has taken a photograph. |
| SCE_COMMON_DIALOG_RESULT_USER_CANCELED | 0x1 | User performed cancel operation. |
| SCE_COMMON_DIALOG_RESULT_ABORTED | 0x2 | Abortion through <code>sceCameraImportDialogAbort()</code> |

Stores one of the following error codes (negative value) for errors. For details, refer to the "Return Codes" section.

Supplementary photographic image information is stored in *output*. For details, refer to the `SceCameraImportDialogOutputParam` section. This is only valid if *result* is `SCE_COMMON_DIALOG_RESULT_OK`.

reserved is a reserved area for future function expansion. It must be filled with all 0s.

Also, photographic image data is stored in the location specified with either the `SceCameraImportDialogMemoryRawParam` or the `SceCameraImportDialogMemoryJpegParam` structure. It is not included in the `SceCameraImportDialogResult` structure.

See Also

`sceCameraImportDialogGetResult()`, `sceCameraImportDialogAbort()`,
`SceCameraImportDialogOutputParam`

SceCameraImportDialogOutputParam

Structure for transmission of supplementary photographic image information

Definition

```
#include <cameraimport_dialog.h>
typedef struct SceCameraImportDialogOutputParam {
    SceSize size;
    SceUInt32 width;
    SceUInt32 height;
    SceUInt32 device;
    SceUInt32 orientation;
    SceChar8 reserved[32];
} SceCameraImportDialogOutputParam;
```

Members

| | |
|--------------------|---------------------------------------|
| <i>size</i> | Size of image data (byte) |
| <i>width</i> | Height of image (pixel) |
| <i>height</i> | Format of image (pixel) |
| <i>device</i> | Device used for taking the photograph |
| <i>orientation</i> | Image rotation information |
| <i>reserved</i> | Reserved area (fill with all 0s) |

Description

This is a structure for receiving supplementary photographic image information. It is included in `SceCameraImportDialogResult`. Fill it with all 0s during initialization.

The size of output photograph data is stored in byte units in *size*.

The width and height of photographed images is stored in pixel units in *width* and *height* respectively.

Information on the device used for taking the photograph is stored in *device*. Specific values are as follows:

| Value | Value | Description |
|--|-------|--|
| <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_DEVICE_FRONT</code> | 0x01 | The camera installed on the same side of the display |
| <code>SCE_CAMERAIMPORT_DIALOG_CAMERA_DEVICE_REAR</code> | 0x02 | The camera installed on the opposite side of the display |

Image rotation information calculated from the values of the acceleration sensor when the photograph is taken is stored in *orientation*. In the case of JPEG format output, the same information will be stored inside the JPEG data. Therefore, no further processing is necessary if displaying JPEG with a rotation information-enabled viewer. In the case of RAW output, the same appearance as at the time the photograph was taken can be reproduced by rotating and displaying the image on the memory in accordance with the value indicated in *orientation*. A valid value for rotation information will only be stored if `SCE_CAMERAIMPORT_DIALOG_ROTATION_MODE_ENABLE` is specified in the *rotationMode* of the `SceCameraImportDialogParam` structure.

| Value | Value | Description |
|---|-------|--|
| <code>SCE_CAMERAIMPORT_DIALOG_IMAGE_ORIENTATION_NORMAL</code> | 0 | If image data is displayed as it is, appearance will be the same as at the time the photograph was taken |

SCE CONFIDENTIAL

| Value | Value | Description |
|---|-------|--|
| SCE_CAMERAIMPORT_DIALOG_IMAGE_ORIENTATION_CLOCKWISE_90 | 1 | If image data is rotated 90 degrees clockwise when displayed, appearance will be the same as at the time the photograph was taken |
| SCE_CAMERAIMPORT_DIALOG_IMAGE_ORIENTATION_CLOCKWISE_180 | 2 | If image data is rotated 180 degrees when displayed, appearance will be the same as at the time the photograph was taken |
| SCE_CAMERAIMPORT_DIALOG_IMAGE_ORIENTATION_CLOCKWISE_270 | 3 | If image data is rotated 270 degrees clockwise when displayed, appearance will be the same as at the time the photograph was taken |

reserved is a reserved area for future function expansion.

See Also

SceCameraImportDialogResult, SceCameraImportDialogParam

SCE CONFIDENTIAL

Abortion

000004892117

Document serial number: 000004892117

SCE CONFIDENTIAL

sceCameraImportDialogAbort

Abort call of Camera Import Dialog

Definition

```
#include <cameraimport_dialog.h>
SceInt32 sceCameraImportDialogAbort ()
```

Arguments

None

Return Values

Returns SCE_OK (0) as the value of the function for success.

Returns one of the following error codes (negative value) for errors.

| Value | Hexadecimal | Description |
|--|-------------|--|
| SCE_COMMON_DIALOG_ERROR_NOT_IN_USE | 0x80020411 | sceCameraImportDialogInit () is not called |
| SCE_COMMON_DIALOG_ERROR_UNEXPECTED_FATAL | 0x8002047F | Internal error |

Description

This function aborts calling of Camera Import Dialog.

It can be called at any time between when sceCameraImportDialogInit () is called and sceCameraImportDialogTerm () is called. If it is called at times other than the above, SCE_COMMON_DIALOG_ERROR_NOT_IN_USE is returned.

When calling is successful, Camera Import Dialog starts to terminate processing, and the operation status will change to SCE_COMMON_DIALOG_STATUS_FINISHED after the completion of the termination processing.

For details on the operation statuses, refer to the sceCameraImportDialogGetStatus () section.

When Camera Import Dialog is closed with this function, calling sceCameraImportDialogGetResult () returns the following.

```
SceCameraImportDialogResult.result : SCE_COMMON_DIALOG_RESULT_ABORTED
```

sceCameraImportDialogAbort () is used to promptly abort the Camera Import Dialog display, for example when an urgent interrupt must be processed.

This function is multithread safe.

See Also

sceCameraImportDialogGetStatus (), sceCameraImportDialogGetResult ()

Termination

000004892117

SCE CONFIDENTIAL

sceCameraImportDialogTerm

End call of Camera Import Dialog

Definition

```
#include <cameraimport_dialog.h>
SceInt32 sceCameraImportDialogTerm()
```

Arguments

None

Return Values

Returns SCE_OK (0) as the value of the function for success.

Returns one of the following error codes (negative value) for errors.

| Value | Hexadecimal | Description |
|--|-------------|---|
| SCE_COMMON_DIALOG_ERROR_NOT_FINISHED | 0x80020410 | Called during other than the appropriate operation status (details below) |
| SCE_COMMON_DIALOG_ERROR_NOT_IN_USE | 0x80020411 | sceCameraImportDialogInit() is not called |
| SCE_COMMON_DIALOG_ERROR_UNEXPECTED_FATAL | 0x8002047F | Internal error |

Description

This function ends calling of Camera Import Dialog. Calling must be ended with this function after Camera Import Dialog has been called with sceCameraImportDialogInit().

This function can be called only while the operation status of Camera Import Dialog is SCE_COMMON_DIALOG_STATUS_FINISHED. If it is called during times other than the above, SCE_COMMON_DIALOG_ERROR_NOT_FINISHED is returned. SCE_COMMON_DIALOG_ERROR_NOT_IN_USE will be returned if the Camera Import Dialog function is not called.

If calling this function is successful, the operation status changes immediately to SCE_COMMON_DIALOG_STATUS_NONE.

For details on the operation statuses, refer to the sceCameraImportDialogGetStatus() section.

This function is multithread safe.

See Also

sceCameraImportDialogInit(), sceCameraImportDialogGetResult()

Constants

000004892117

Return Codes

List of return codes returned by Camera Import Dialog

Definition

| Value | Hexadecimal | Description |
|--|-------------|---|
| SCE_COMMON_DIALOG_ERROR_BUSY | 0x80020401 | Calling another common dialog function |
| SCE_COMMON_DIALOG_ERROR_NULL | 0x80020402 | NULL was specified as the function's argument |
| SCE_COMMON_DIALOG_ERROR_INVALID_ARGUMENT | 0x80020403 | Parameter error |
| SCE_COMMON_DIALOG_ERROR_NOT_RUNNING | 0x80020404 | Called during a period other than SCE_COMMON_DIALOG_STATUS_RUNNING |
| SCE_COMMON_DIALOG_ERROR_NOT_FINISHED | 0x80020410 | Called during a period other than SCE_COMMON_DIALOG_STATUS_FINISHED |
| SCE_COMMON_DIALOG_ERROR_NOT_IN_USE | 0x80020411 | sceCameraImportDialogInit() is not called |
| SCE_COMMON_DIALOG_ERROR_UNEXPECTED_FATAL | 0x8002047F | Internal error |
| SCE_CAMERAIMPORT_DIALOG_ERROR_CAMERA_ALREADY_USED | 0x80104701 | libcamera is in use within a process |
| SCE_CAMERAIMPORT_DIALOG_ERROR_REQUIRED_DEVICE_CANNOT_USE | 0x80104704 | Required device cannot be used |